




Cisco Packet Tracer

File Edit Options View Tools Extensions Window Help

Logical Physical x: 598, y: 341 [Root]

Router0

Physical Config CLI Attributes

IOS Command Line Interface

```
Router>enable
Router#
Router#sh ip int brief
Interface      IP-Address      OK? Method Status
Protocol
FastEthernet0/0 141.1.0.1       YES manual up
FastEthernet0/1 141.2.0.1       YES manual up
Vlan1          unassigned      YES unset  administratively down down
Router#ping 141.1.0.111

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 141.1.0.111, timeout is 2 seconds:
.....
Success rate is 80 percent (4/5), round-trip min/avg/max = 0/3/13 ms

Router#ping 141.1.0.1

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 141.1.0.1, timeout is 2 seconds:
.....
Success rate is 100 percent (5/5), round-trip min/avg/max = 0/7/15 ms

Router#ping 141.2.0.111

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 141.2.0.111, timeout is 2 seconds:
.....
Success rate is 80 percent (4/5), round-trip min/avg/max = 0/0/1 ms

Router#
```

Ctrl+F6 to exit CLI focus

Copy Paste

Time: 01:02:30

Scenario 0


New Delete


Toggle PDU List Window


Fire Last Status Source Destination Type Color Time(sec) Periodic Num Edit Delete


Copper Cross-Over


3:11 PM 7/10/2026











Cisco Packet Tracer

File Edit Options View Tools Extensions Window Help

Logical Physical x: 430, y: 374

Router0

Physical Config CLI Attributes

IOS Command Line Interface

Interface	IP-Address	OK?	Method	Status
FastEthernet0/0	141.1.0.1	YES	manual	up
FastEthernet0/1	141.2.0.1	YES	manual	down
Vlan1	unassigned	YES	unset	administratively down

Router#

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up

Router#sh ip int brief

Interface	IP-Address	OK?	Method	Status
FastEthernet0/0	141.1.0.1	YES	manual	up
FastEthernet0/1	141.2.0.1	YES	manual	up
Vlan1	unassigned	YES	unset	administratively down

Router#line console 0

% Invalid input detected at '' marker.

Router#config t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#line console 0

Router(config-line)#password 123

Router(config-line)#login

Router(config-line)#exit

Router(config)#exit

Router#

%SYS-5-CONFIG_I: Configured from console by console

Router#exit

Ctrl+F6 to exit CLI focus

Copy Paste

Time: 00:35:15

Realtime Simulation

Scenario 0

New Delete

Toggle PDU List Window

Copper Cross-Over

Search

2:43 PM 7/10/2026