



QUANTUM PROGRAMS

Anton Karazeev

Department of Innovation
and High Technologies

MIPT, 2017

Outline

- Applications of quantum computers
- Building blocks of QC
- IBM Q experience

Paper

A Software Methodology for Compiling Quantum Programs

Thomas Häner,¹ Damian S. Steiger,¹ Krysta Svore,² and Matthias Troyer^{1, 2, 3}

¹*Theoretische Physik, ETH Zurich, 8093 Zurich, Switzerland*

²*Quantum Architectures and Computation Group, Microsoft Research, Redmond, WA (USA)*

³*Microsoft Research Station Q, Santa Barbara, CA (USA)*

Quantum computers promise to transform our notions of computation by offering a completely new paradigm. To achieve scalable quantum computation, optimizing compilers and a corresponding software design flow will be essential. We present a software architecture for compiling quantum programs from a high-level language program to hardware-specific instructions. We describe the necessary layers of abstraction and their differences and similarities to classical layers of a computer-aided design flow. For each layer of the stack, we discuss the underlying methods for compilation and optimization. Our software methodology facilitates more rapid innovation among quantum algorithm designers, quantum hardware engineers, and experimentalists. It enables scalable compilation of complex quantum algorithms and can be targeted to any specific quantum hardware implementation.

Keywords: Quantum Computing, Compilers, Quantum Programming Languages

I. INTRODUCTION

The field of high-performance computing will be revolutionized by the introduction of scalable quantum computers. Today, the majority of high-performance computing time is dedicated to solving problems in quantum chemistry and materials science. These problems would dramatically benefit from better classical algorithms or new models of computation that further reduce the processing time. One such model, as suggested by Richard Feynman [1], is *quantum computation*, which takes advantage of quantum mechanics to obtain expo-




Figure 1. Quantum computers will be used as accelerators

<https://arxiv.org/abs/1604.01401> [2016]

Applications of quantum computers

- Materials science
- Cryptography
- Machine learning

<https://arxiv.org/abs/1604.01401>

Building blocks of QC

$$\alpha |0\rangle + \beta |1\rangle = \alpha \begin{pmatrix} 1 \\ 0 \end{pmatrix} + \beta \begin{pmatrix} 0 \\ 1 \end{pmatrix} = \begin{pmatrix} \alpha \\ \beta \end{pmatrix}$$

The state of one qubit

<https://arxiv.org/abs/1604.01401>

Building blocks of QC

$$\alpha |0\rangle + \beta |1\rangle = \alpha \begin{pmatrix} 1 \\ 0 \end{pmatrix} + \beta \begin{pmatrix} 0 \\ 1 \end{pmatrix} = \begin{pmatrix} \alpha \\ \beta \end{pmatrix}$$

The state of one qubit

$$\begin{pmatrix} \alpha_0 \\ \alpha_1 \end{pmatrix} \otimes \begin{pmatrix} \beta_0 \\ \beta_1 \end{pmatrix} = \begin{pmatrix} \alpha_0\beta_0 \\ \alpha_0\beta_1 \\ \alpha_1\beta_0 \\ \alpha_1\beta_1 \end{pmatrix}$$

The state of the entire system
with two qubits

<https://arxiv.org/abs/1604.01401>

Building blocks of QC

$$\alpha |0\rangle + \beta |1\rangle = \alpha \begin{pmatrix} 1 \\ 0 \end{pmatrix} + \beta \begin{pmatrix} 0 \\ 1 \end{pmatrix} = \begin{pmatrix} \alpha \\ \beta \end{pmatrix}$$

The state of one qubit

$$\begin{pmatrix} \alpha_0 \\ \alpha_1 \end{pmatrix} \otimes \begin{pmatrix} \beta_0 \\ \beta_1 \end{pmatrix} = \begin{pmatrix} \alpha_0\beta_0 \\ \alpha_0\beta_1 \\ \alpha_1\beta_0 \\ \alpha_1\beta_1 \end{pmatrix}$$

The state of the entire system
with two qubits


Gate	Matrix	Symbol
NOT or X gate	$\begin{pmatrix} 0 & 1 \\ 1 & 0 \end{pmatrix}$	
Controlled NOT (CNOT)	$\begin{pmatrix} 1 & 0 & 0 & 0 \\ 0 & 1 & 0 & 0 \\ 0 & 0 & 0 & 1 \\ 0 & 0 & 1 & 0 \end{pmatrix}$	

Gates (to change qubit's state)

<https://arxiv.org/abs/1604.01401>

Quantum circuits

Apply a NOT gate to the first qubit, then a CNOT gate



$$|00\rangle \rightarrow |11\rangle$$


$$|01\rangle \rightarrow |10\rangle$$

$$|10\rangle \rightarrow |00\rangle$$

$$|11\rangle \rightarrow |01\rangle$$


Quantum circuits

Apply a NOT gate to the first qubit, then a CNOT gate



$$\begin{aligned} |00\rangle &\rightarrow |11\rangle \\ |01\rangle &\rightarrow |10\rangle \\ |10\rangle &\rightarrow |00\rangle \\ |11\rangle &\rightarrow |01\rangle \end{aligned}$$

Apply a NOT gate to the second qubit, then a CNOT gate



$$\begin{aligned} |00\rangle &\rightarrow |01\rangle \\ |01\rangle &\rightarrow |00\rangle \\ |10\rangle &\rightarrow |10\rangle \\ |11\rangle &\rightarrow |11\rangle \end{aligned}$$

Quantum circuits

Apply a NOT gate to the first qubit, then a CNOT gate

$$1. X \otimes \mathbb{1}_2 = \begin{pmatrix} 0 & 1 \\ 1 & 0 \end{pmatrix} \otimes \begin{pmatrix} 1 & 0 \\ 0 & 1 \end{pmatrix} = \begin{pmatrix} 0 & 0 & 1 & 0 \\ 0 & 0 & 0 & 1 \\ 1 & 0 & 0 & 0 \\ 0 & 1 & 0 & 0 \end{pmatrix}$$

$$2. \begin{pmatrix} 0 & 0 & 1 & 0 \\ 0 & 0 & 0 & 1 \\ 1 & 0 & 0 & 0 \\ 0 & 1 & 0 & 0 \end{pmatrix} \cdot \begin{pmatrix} \alpha_0\beta_0 \\ \alpha_0\beta_1 \\ \alpha_1\beta_0 \\ \alpha_1\beta_1 \end{pmatrix} = \begin{pmatrix} \alpha_1\beta_0 \\ \alpha_1\beta_1 \\ \alpha_0\beta_0 \\ \alpha_0\beta_1 \end{pmatrix}$$

$$3. \begin{pmatrix} 1 & 0 & 0 & 0 \\ 0 & 1 & 0 & 0 \\ 0 & 0 & 0 & 1 \\ 0 & 0 & 1 & 0 \end{pmatrix} \cdot \begin{pmatrix} \alpha_1\beta_0 \\ \alpha_1\beta_1 \\ \alpha_0\beta_0 \\ \alpha_0\beta_1 \end{pmatrix} = \begin{pmatrix} \alpha_1\beta_0 \\ \alpha_1\beta_1 \\ \alpha_0\beta_1 \\ \alpha_0\beta_0 \end{pmatrix}$$

$$|00\rangle \rightarrow |11\rangle$$

$$|01\rangle \rightarrow |10\rangle$$

$$|10\rangle \rightarrow |00\rangle$$

$$|11\rangle \rightarrow |01\rangle$$

Apply a NOT gate to the second qubit, then a CNOT gate

$$1. \mathbb{1}_2 \otimes X = \begin{pmatrix} 1 & 0 \\ 0 & 1 \end{pmatrix} \otimes \begin{pmatrix} 0 & 1 \\ 1 & 0 \end{pmatrix} = \begin{pmatrix} 0 & 1 & 0 & 0 \\ 1 & 0 & 0 & 0 \\ 0 & 0 & 0 & 1 \\ 0 & 0 & 1 & 0 \end{pmatrix}$$

$$2. \begin{pmatrix} 0 & 1 & 0 & 0 \\ 1 & 0 & 0 & 0 \\ 0 & 0 & 0 & 1 \\ 0 & 0 & 1 & 0 \end{pmatrix} \cdot \begin{pmatrix} \alpha_0\beta_0 \\ \alpha_0\beta_1 \\ \alpha_1\beta_0 \\ \alpha_1\beta_1 \end{pmatrix} = \begin{pmatrix} \alpha_0\beta_1 \\ \alpha_0\beta_0 \\ \alpha_1\beta_1 \\ \alpha_1\beta_0 \end{pmatrix}$$

$$3. \begin{pmatrix} 1 & 0 & 0 & 0 \\ 0 & 1 & 0 & 0 \\ 0 & 0 & 0 & 1 \\ 0 & 0 & 1 & 0 \end{pmatrix} \cdot \begin{pmatrix} \alpha_0\beta_1 \\ \alpha_0\beta_0 \\ \alpha_1\beta_1 \\ \alpha_1\beta_0 \end{pmatrix} = \begin{pmatrix} \alpha_0\beta_1 \\ \alpha_0\beta_0 \\ \alpha_1\beta_0 \\ \alpha_1\beta_1 \end{pmatrix}$$

$$|00\rangle \rightarrow |01\rangle$$

$$|01\rangle \rightarrow |00\rangle$$

$$|10\rangle \rightarrow |10\rangle$$

$$|11\rangle \rightarrow |11\rangle$$

Quantum circuits

Apply a NOT gate to the first qubit, then a CNOT gate

```
# import the operations we want to perform
from projectq.ops import Measure, CNOT, NOT
from projectq.backends import CircuitDrawer
from projectq import MainEngine

eng = MainEngine()

b1 = eng.allocate_qubit() # allocate `b1` qubit
b2 = eng.allocate_qubit() # allocate `b2` qubit

Measure | b1 # measure the qubit
Measure | b2 # measure the qubit
print("(1) b1: {}".format(int(b1))) # measure the `b1` qubit
print("(1) b2: {}\\n--".format(int(b2))) # measure the `b2` qubit

NOT | b1
CNOT | (b1, b2)

Measure | b1 # measure the qubit
Measure | b2 # measure the qubit

eng.flush()
print("(2) b1: {}".format(int(b1))) # output measurement result
print("(2) b2: {}".format(int(b2))) # output measurement result

(1) b1: 0
(1) b2: 0
--
(2) b1: 1
(2) b2: 1
```

Apply a NOT gate to the second qubit, then a CNOT gate

```
# import the operations we want to perform
from projectq.ops import Measure, CNOT, NOT
from projectq.backends import CircuitDrawer
from projectq import MainEngine

eng = MainEngine()

b1 = eng.allocate_qubit() # allocate `b1` qubit
b2 = eng.allocate_qubit() # allocate `b2` qubit

Measure | b1 # measure the qubit
Measure | b2 # measure the qubit
print("(1) b1: {}".format(int(b1))) # measure the `b1` qubit
print("(1) b2: {}\\n--".format(int(b2))) # measure the `b2` qubit

NOT | b2
CNOT | (b1, b2)

Measure | b1 # measure the qubit
Measure | b2 # measure the qubit

eng.flush()
print("(2) b1: {}".format(int(b1))) # output measurement result
print("(2) b2: {}".format(int(b2))) # output measurement result

(1) b1: 0
(1) b2: 0
--
(2) b1: 0
(2) b2: 1
```

IBM Q experience

CNOT (input 10)

Add a description New Save Save as

Switch to Qasm Editor Backend: Custom Topology My Units: 11 Experiment Units: 3 Simulate

GATES Advanced

id	X	Y	Z	H
S	S^\dagger	+	T	T^\dagger


BARRIER

OPERATIONS

<https://quantumexperience.ng.bluemix.net>

IBM Q experience

Backend: ibmqx4 (5 Qubits) ACTIVE



Date Calibration: 2017-12-07 13:59:48 Fridge Temperature: 0.021 K [More details](#)

	Q0	Q1	Q2	Q3	Q4
Gate Error (10^{-3})	0.86	0.52	1.29	1.63	1.55
Readout Error (10^{-2})	3.80	4.70	4.60	3.70	7.20
MultiQubit Gate Error (10^{-2})	CX1_0 1.66	CX2_0 3.82	CX3_2 2.42		
	CX2_1 5.80	CX3_4 2.83			
	CX2_4 5.03				


> Backend: ibmqx5 (16 Qubits) ACTIVE


> Backend: ibmqx2 (5 Qubits) MAINTENANCE

<https://quantumexperience.ng.bluemix.net>


IBM Q experience

CNOT (input 10) 

 **Switch to Qasm Editor**



Simulation



<https://quantumexperience.ng.bluemix.net>

Summary

- Applications of quantum computers
- Qubits and gates
- IBM Q experience

References

- Source for image on title slide: <https://www.linkedin.com/pulse/quantum-computing-innovation-disrupt-silicon-valley-cami-rosso>
- Source for image on other slides: <https://hackernoon.com/google-plans-to-introduce-a-cloud-service-for-quantum-computing-74f47d808490>
- Quantum circuits were drawn using ProjectQ framework for Python: <https://github.com/ProjectQ-Framework/ProjectQ>