

```
1 Console.WriteLine("Give an integer number:");
2 int number = Convert.ToInt32(Console.ReadLine());
3
4 if (number % 2 == 0)
5 {
6     Console.WriteLine($"{number} Even");
7 }
8 else
9 {
10    Console.WriteLine($"{number} Odd");
11 }
12
```

Problems Output Debug Console Terminal Ports

```
PS C:\Users\12588063\Documents\ConsoleApp1> & 'c:\Users\12588063\.vscode\extensions\ms-dotnettools.csharp-2.140.9-win32-x64\debugger\x86_64\vsdbg.exe' '--interpreter=vscode' '--connection=5db75f90fbc94e679a4ca7d8cbc062e9'
Give an integer number:
1
1 Odd
PS C:\Users\12588063\Documents\ConsoleApp1>
```

1.

```
1 {
2 {
3     int i = 1;
4
5     do
6     {
7         Console.WriteLine(i);
8         i++;
9     } while (i <= 5);
10 }
11 }
12
13
```

Problems Output Debug Console Terminal Ports

```
PS C:\Users\12588063\Documents\ConsoleApp1> & 'c:\Users\12588063\.vscode\extensions\ms-dotnettools.csharp-2.140.9-win32-x64\debugger\x86_64\vsdbg.exe' '--interpreter=vscode' '--connection=fe6cdec808824c9d957a4f5dc4984917'
1
2
3
4
5
PS C:\Users\12588063\Documents\ConsoleApp1>
```

2.

```
1 {
2   {
3     int num = 2;
4
5     while (num <= 10)
6     {
7       Console.WriteLine(num);
8       num += 2;
9     }
10  }
11 }
12
```

Problems Output Debug Console Terminal Ports

2
4
6
8
10

The program '[23432] ConsoleApp5.exe' has exited with code 0 (0x0).

3.

```
1 Console.WriteLine("What is your speed");
2 int speed = Convert.ToInt32(Console.ReadLine());
3 if (speed < 60)
4 {
5   Console.WriteLine("Within Speed Limit");
6 }
7 else if (speed >= 60 )
8 {
9   Console.WriteLine("Over Speed Limit");
10 }
11 else
12 {
13   Console.WriteLine("Invalid Input");
14 }
15
```

Problems Output Debug Console Terminal Ports

PS C:\Users\12588063\Documents\ConsoleApp1> & 'c:\Users\12588063\.vscode\extensions\ms-dotnettools.csharp-2.140.9-win32-x64\debugger\x86_64\vsdbg.exe' '--interpreter=vscode' '--connection=3809ef77435c49ce94e41aa9d0eb9bf2'

What is your speed
90
Over Speed Limit
PS C:\Users\12588063\Documents\ConsoleApp1>
PS C:\Users\12588063\Documents\ConsoleApp1> & 'c:\Users\12588063\.vscode\extensions\ms-dotnettools.csharp-2.140.9-win32-x64\debugger\x86_64\vsdbg.exe' '--interpreter=vscode' '--connection=f812db45939641edb6775c5d13324146'

What is your speed
58
Within Speed Limit

4.

```
1 {
2 {
3     Console.WriteLine("Enter your role (admin, editor, viewer):");
4     string userRole = Console.ReadLine();
5
6     string accessLevel = userRole?.ToLower() switch
7     {
8         "admin" => "Full Access: Read, Write, Delete, and Manage Users.",
9         "editor" => "Modify Access: Read, Write, and Edit content.",
10        "viewer" => "Limited Access: Read-only.",
11        _ => "Access Denied: Invalid or unknown role."
12    };
13
14    Console.WriteLine($"Role: {userRole} -> {accessLevel}");
15 }
16 }
17
```

Problems Output Debug Console Terminal Ports

```
PS C:\Users\12588063\Documents\ConsoleApp1> & 'c:\Users\12588063\.vscode\extensions\ms-dotnettools.csharp-2.148.9-win32-x64\debugger\x86_64\vsdbg.exe' '--interpreter=vscode' '--connection=bc42cd19e317428db0e452cabf1742bb'
Role: admin -> Full Access: Read, Write, Delete, and Manage Users.
PS C:\Users\12588063\Documents\ConsoleApp1> & 'c:\Users\12588063\.vscode\extensions\ms-dotnettools.csharp-2.148.9-win32-x64\debugger\x86_64\vsdbg.exe' '--interpreter=vscode' '--connection=fac3d26fb56c4b65a2427c7da100fcdb'
Enter your role (admin, editor, viewer):
admin
Role: admin -> Full Access: Read, Write, Delete, and Manage Users.
PS C:\Users\12588063\Documents\ConsoleApp1> & 'c:\Users\12588063\.vscode\extensions\ms-dotnettools.csharp-2.148.9-win32-x64\debugger\x86_64\vsdbg.exe' '--interpreter=vscode' '--connection=c0f84d6eb72b4e7ca31226f1996f3c54'
Enter your role (admin, editor, viewer):
editor
Role: editor -> Modify Access: Read, Write, and Edit content.
PS C:\Users\12588063\Documents\ConsoleApp1> & 'c:\Users\12588063\.vscode\extensions\ms-dotnettools.csharp-2.148.9-win32-x64\debugger\x86_64\vsdbg.exe' '--interpreter=vscode' '--connection=a8268780e60141f48ff1bba26c16d0b8'
Enter your role (admin, editor, viewer):
viewer
Role: viewer -> Limited Access: Read-only.
PS C:\Users\12588063\Documents\ConsoleApp1>
```

5.