

WETH Staking Platform

User Guide - How to Use Every Feature

This is a test environment. Everything on this platform runs on **Robinhood Chain Testnet**, not the real Robinhood Chain. Every token here (WETH, RWD, tRWD, LP tokens) is a test token with **no real monetary value**. Connecting a wallet, staking, farming, and swapping cost nothing - transaction fees are paid in free testnet gas, not real money.

This platform lets you deposit tokens to earn rewards ("staking" and "farming"), and trade one token for another ("swapping") - all without a bank or broker in the middle. This guide walks through every screen and button, in plain terms.

1. Getting Started

What you need

- A browser wallet - **MetaMask** is what this platform has been tested with (free browser extension: metamask.io).
- Your wallet connected to the **Robinhood Chain Testnet** network (not Mainnet).
- A small amount of **testnet ETH** in that wallet, used only to pay transaction fees. This is free - request it from a Robinhood Chain testnet faucet, it is not real money.

Connecting your wallet

- 1 Open the site and click **Connect Wallet** (or "Start staking") in the top-right corner.
- 2 Choose MetaMask (or your wallet of choice) and approve the connection request.
- 3 Confirm the network selector at the top shows **"Robinhood Chain Testnet"**. If it shows something else, switch networks from that same dropdown.

2. Platform Map

The top navigation bar has five destinations. Each is a separate feature - here is what each one is for, at a glance:

Menu	What it does
Stake	Deposit WETH, earn a separate reward token (tRWD). Fixed reward budget, refilled periodically.

Farm	Deposit WETH - or LP tokens from the Pool page - earn RWD, freshly issued every second, never runs out.
Stake RWD	Lock up RWD you've already earned to earn more RWD on top of it.
Pool	Swap WETH <-> RWD directly, or add/remove liquidity to the WETH/RWD trading pool.
Security	Jumps to the security section on the homepage - background info, not an action page.

Why are there two "staking" pages? "Stake" and "Stake RWD" are two separate, independent pools with different tokens on each side - Stake takes WETH and pays tRWD; Stake RWD takes RWD and pays RWD. They are kept deliberately separate so the two token flows never get mixed up.

3. Stake - Deposit WETH, Earn tRWD

A fixed-term reward pool. The team funds a reward budget for a set period (currently 7 days); everyone who has WETH staked during that period shares the reward, proportional to how much they staked and for how long.

Screen layout

Total value locked	Total WETH everyone has staked in this pool right now.
Your WETH balance	How much WETH is in your connected wallet.
Staked / Earned	How much you personally have staked, and how much tRWD you've earned so far.

How to stake

- 1 Enter an amount in the input box (or click **Max** to use your full balance).
- 2 Click **Approve** - a one-time permission letting the contract move your WETH. Confirm this in your wallet popup.
- 3 Click **Stake** and confirm in your wallet. Your position now starts earning tRWD.

Other actions

- **Withdraw** - pull some or all of your staked WETH back out.
- **Claim reward** - collect your earned tRWD without withdrawing your stake.
- **Exit** - withdraw everything and claim your reward in a single transaction.

4. Farm - Deposit WETH or LP Tokens, Earn RWD

Unlike Stake, RWD here is minted fresh every second - the reward never runs dry. The Farm page has **two separate pools** stacked on the same page:

- **WETH pool** - deposit WETH directly, earn RWD.
- **WETH-RWD-LP pool** - deposit the LP token you receive from adding liquidity on the Pool page (see Section 6), also earns RWD. This rewards people who help provide the trading liquidity, on top of the trading fees they already earn.

Both pools work identically - the same Deposit / Withdraw / Harvest / Emergency Withdraw actions described below, just with a different token going in.

How to farm

- 1 Enter an amount and click **Approve**, then confirm in your wallet.
- 2 Click **Deposit** and confirm. You start earning RWD immediately, every second.
- 3 Click **Harvest** any time to collect pending RWD without withdrawing your stake.

- 4 Click **Withdraw** to pull some or all of your deposit back out (this also pays out any pending reward automatically).

Emergency withdraw instantly returns your deposit but **forfeits any unclaimed reward**. Use this only if you need your funds back immediately and don't mind losing pending rewards.

RWD Supply panel (bottom of the Farm page)

A read-only dashboard showing the total RWD supply and how much has been newly minted in the last 7 and 30 days - useful for keeping an eye on how quickly new RWD is being created over time.

5. Stake RWD - Compound Your RWD

Works exactly like the Stake page (Section 3), but both sides use RWD: lock up RWD you've earned from farming, earn more RWD on top of it over time from a separately funded reward budget. The two amounts shown - what you've staked and what you've earned - are both in RWD, so look closely at the labels to tell them apart.

The same Approve -> Stake -> Withdraw / Claim reward / Exit actions from Section 3 apply here.

6. Pool - Swap and Provide Liquidity

The Pool page holds the WETH/RWD trading pool. It shows current reserves and price, and offers three actions: Swap, Add Liquidity, and Remove Liquidity.

Swapping

- 1 Choose a direction with **Switch direction** (WETH -> RWD or RWD -> WETH).
- 2 Enter the amount you want to trade in. The estimated amount you'll receive updates live.
- 3 Click **Approve** (first time for that token), then **Swap**, and confirm in your wallet.

Price impact warning. If your trade is large relative to how much liquidity is currently in the pool, the app shows a price-impact percentage. Above 10% it turns red and you must tick a confirmation box before the Swap button unlocks - this exists specifically to stop an oversized trade from accidentally draining a shallow pool and wrecking the price for everyone. If you see this warning, consider trading a smaller amount instead.

Adding liquidity

Depositing both WETH and RWD together makes you a liquidity provider - you earn a share of every trading fee going forward. In exchange you receive an LP token ("WETH-RWD-LP"), which represents your share of the pool and can also be staked on the Farm page for extra RWD rewards (Section 4).

- 1 Enter an amount in either the WETH or RWD box - the other box auto-fills to match the pool's current ratio, so you don't have to calculate it yourself.
- 2 Click **Approve WETH** and **Approve RWD** (both are needed, one time each).
- 3 Click **Add** and confirm. You receive LP tokens representing your share.

Removing liquidity

- 1 Enter how many LP tokens to redeem (or click **Max** for your full balance).
- 2 Review the estimated WETH + RWD you'll receive back.
- 3 Click **Remove** and confirm - no separate approval step is needed here.

7. Glossary

Plain-language definitions for the terms used across the platform.

Wallet	An app (like MetaMask) that holds your tokens and signs transactions on your behalf. Nobody else can move your funds without your wallet's approval.
Testnet	A practice version of a blockchain used for testing. Tokens here have no real value, unlike the real ("Mainnet") network.
Gas	The small fee paid to process a transaction. On testnet this is a free test token, not real money.
Staking / Farming	Depositing tokens into a contract to earn rewards over time, instead of letting them sit idle.
APR	Annual Percentage Rate - an estimate of yearly return if current conditions held steady all year. Shown as a % (e.g. "12% APR").
TVL	Total Value Locked - the total value of everything currently deposited in a pool.
Liquidity Pool	A pot of two tokens (here, WETH and RWD) that lets people swap one for the other automatically, without a buyer/seller match needed.
LP Token	A receipt token you get for depositing into a liquidity pool, representing your share of it. Can be redeemed for your share of the underlying tokens.
Swap	Trading one token directly for another through the liquidity pool.
Slippage	The gap between the price you expected and the price you actually got, due to the trade itself moving the price slightly. This platform applies a small automatic tolerance (0.5%) to protect you.
Price impact	How much your own trade moves the pool's price. Large trades against a small pool cause large price impact - see the warning box in Section 6.
Mint / Burn	"Mint" creates new tokens out of nothing (increasing total supply); "burn" permanently destroys tokens (decreasing total supply).
Uncapped supply	A token with no maximum limit - more can always be minted, unlike a token with a fixed total supply.

This guide covers the Robinhood Chain Testnet deployment of the WETH Staking platform. Contract addresses and technical details are tracked separately in the project's internal handoff documentation.