


SPRING FRAMEWORK




Spring Bean Lifecycle

Spring Bean Life Cycle




Spring Bean Life Cycle

Container Shutdown



Disposable Bean's destroy()



Call Custom Destroy Method



Callback Interfaces

- Spring has two interfaces you can implement for call back events
- InitializingBean.afterPropertiesSet()
 - called after properties are set
- DisposableBean.destroy()
 - Called during bean destruction in shutdown

Life Cycle Annotations

- Spring has two annotations you can use to hook into the bean life cycle
- @PostConstruct annotated methods will be called after the bean has been constructed, but before its returned to the requesting object
- @PreDestroy is called just before the bean is destroyed by the container

Bean Post Processors

- Gives you a means to tap into the Spring context life cycle and interact with beans as they are processed
- Implement interface BeanPostProcessor
 - postProcessBeforeInitialization Called before bean initialization method
 - postProcessAfterInitialization Called after bean initialization

'Aware' Interfaces

- Spring has over 14 'Aware' interfaces.
- These are used to access the Spring Framework infrastructure
- These are largely used within the framework
- Rarely used by Spring developers

'Aware' Interfaces

Aware Interface	Description
ApplicationContextAware	Interface to be implemented by any object that wishes to be notified of the ApplicationContext that it runs in.
ApplicationEventPublisherAware	Set the ApplicationEventPublisherthat this object runs in.
BeanClassLoaderAware	Callback that supplies the bean class loader to a bean instance.
BeanFactoryAware	Callback that supplies the owning factory to a bean instance.
BeanNameAware	Set the name of the bean in the bean factory that created this bean.
BootstrapContextAware	Set the BootstrapContext that this object runs in.

Aware Interface	Description
LoadTimeWeaverAware	Set the LoadTimeWeaver of this object's containing ApplicationContext.
MessageSourceAware	Set the MessageSource that this object runs in.
NotificationPublisherAware	Set the NotificationPublisher instance for the current managed resource instance.
PortletConfigAware	Set the PortletConfig this object runs in.
PortletContextAware	Set the PortletContext that this object runs in.
ResourceLoaderAware	Set the ResourceLoader that this object runs in.
ServletConfigAware	Set the ServletConfig that this object runs in.
ServletContextAware	Set the ServletContext that this object runs in.



SPRING FRAMEWORK

