E11 – Skineffekt

21. Oktober 2015

Tabelle 1: Kupferrohr

Frequenz (Hz)	Phasenverschiebung (°)	Amplitude (mV)	Shunt-Spannung (mV)
1	2	70.0	195.3
10	19.2	66.0	200.0
20	35.5	57.8	200.0
40	56.7	41.8	200.3
80	76.7	24.4	200.0
120	87	16.9	200.1
160	94	12.7	200.1
200	100	10.0	200.0
400	121	4.8	200.0
600	140	2.9	199.7
800	155	1.9	200.5
1000	170	1.4	200.2
1200	180	1.0	200.0
1500	200	0.7	199.9

Tabelle 2: Rohr aus rostfreiem Stahl

Frequenz (Hz)	Phasenverschiebung (°)	Amplitude (mV)
40	1.8	68.7
120	5.4	69.1
200	9	68.7
400	17.5	66.2
600	25.4	62.7
800	32.4	59
1000	38.4	54.5
1200	43.5	50.5
1500	50	45
1750	54	41
2000	58	37.2
2500	64	32
3500	71	24
5000	78	18
7500	88	12

 ${\bf Tabelle~3:~Vollzylinder~aus~Aluminium,~frequenzabh\"{a}ngig}$

Frequenz (Hz)	Phasenverschiebung (°)	Amplitude (mV)
1	5.4	69
5	26	65
10	50	57
15	69	48
20	85	40
30	111	28.5
40	132	21
60	166	12.5
80	196	8
100	220	5.4
120	243	3.6
160	283	1.9
200	320	1
250	350	0.6

Tabelle 4: Vollzylinder aus Aluminium, $30\,\mathrm{Hz}$

Radius (mm)	Phasenverschiebung (°)	Amplitude (mV)
0	111	28.6
5	109	28.5
10	104	28.7
15	94	29
20	81	30
25	65	33
30	48.5	38
35	32	45
40	16	54
45	2.7	62
50	0	37

Tabelle 5: Vollzylinder aus Aluminium, $450\,\mathrm{Hz}$

Radius (mm)	Phasenverschiebung (°)	Amplitude (mV)
25	215	1.5
27.5	183	2.2
30	152	3.6
32.5	125	5.9
35	100	9.5
37.5	73	15.5
40	47	25
42.5	24	39
45	5.2	55
47.5	0.2	57.5
50	0	38