EcoreDoc Config Model

Table of Contents

Contents of config.	L
Types	L
Abstract Class AEReferenceConfig	L
Class EAttributeConfig	L
Class EClassConfig	L
Class EContainmentConfig	2
Class EDataTypeConfig 2	2
Class EEnumConfig	3
Class EEnumLiteralConfig	3
Class EPackageConfig	3
Class EReferenceConfig	1
Class EcoreDocGeneratorConfig.	1
Interface IDefaultValueConfig	5
Interface IEAttributeConfig.	5
Interface IEClassConfig 5	5
Interface IEClassifierConfig ϵ	3
Interface IEDataTypeConfig	3
Interface IEEnumConfig	3
Interface IEEnumLiteralConfig \cdots	3
Interface IENamedElementConfig6	3
Interface IEPackageConfig.	7
Interface IEReferenceConfig.	7
Interface IEStructuralFeatureConfig	7

Contents of config

Ns Prefix

config

Ns URI

com.altran.general.emf.ecoredoc.generator.config

Types

Abstract Class AEReferenceConfig

Super-types

- config.IDefaultValueConfig
- config.IENamedElementConfig
- config.IEReferenceConfig
- config.IEStructuralFeatureConfig

Class EAttributeConfig

Super-types

- config.IDefaultValueConfig
- config.IEAttributeConfig
- config.IENamedElementConfig
- config.IEStructuralFeatureConfig

References

Name	Туре	Properties	Description
targetEAttribute	ecore.EAttribute	[01]	

Used at

• config.EClassConfig.eAttributes

Class EClassConfig

Super-types

- config.IDefaultValueConfig
- config.IEAttributeConfig
- config.IEClassConfig
- config.IEClassifierConfig
- config.IENamedElementConfig
- config.IEReferenceConfig
- config.IEStructuralFeatureConfig

Containments

Name	Туре	Properties	Description
eAttributes	config. EAttributeConfig	[0*]	
eContainments	config. EContainmentConfig	[0*]	
eReferences	config. EReferenceConfig	[0*]	

References

Name	Туре	Properties	Description
targetEClass	ecore.EClass	[01]	

Used at

• config.EPackageConfig.eClasses

Class EContainmentConfig

Super-types

- config.AEReferenceConfig
- config.IDefaultValueConfig
- config.IENamedElementConfig
- config.IEReferenceConfig
- config.IEStructuralFeatureConfig

References

Name	Туре	Properties	Description
targetEContainment	ecore.EReference	[01]	

Used at

• config.EClassConfig.eContainments

Class EDataTypeConfig

Super-types

- config.IDefaultValueConfig
- config.IEClassifierConfig
- config.IEDataTypeConfig
- config.IENamedElementConfig

References

Name	Туре	Properties	Description
targetEDataType	ecore.EDataType	[01]	

Used at

• config.EPackageConfig.eDataTypes

Class EEnumConfig

Super-types

- config.IDefaultValueConfig
- config.IEClassifierConfig
- config.IEDataTypeConfig
- config.IEEnumConfig
- config.IEEnumLiteralConfig
- config.IENamedElementConfig

Containments

Name	Туре	Properties	Description
eEnumLiterals	config. EEnumLiteralConfig	[0*]	

References

Name	Туре	Properties	Description
targetEEnum	ecore.EEnum	[01]	

Used at

• config.EPackageConfig.eEnums

Class EEnumLiteralConfig

Super-types

- config.IEEnumLiteralConfig
- config.IENamedElementConfig

References

Name	Туре	Properties	Description
targetEEnumLiteral	ecore.EEnumLiteral	[01]	

Used at

• config.EEnumConfig.eEnumLiterals

Class EPackageConfig

Super-types

- config.IDefaultValueConfig
- config.IEAttributeConfig
- config.IEClassConfig
- config.IEClassifierConfig
- config.IEDataTypeConfig
- config.IEEnumConfig
- config.IEEnumLiteralConfig config.IENamedElementConfig

- config.IEPackageConfig
- config.IEReferenceConfig
- config.IEStructuralFeatureConfig

Containments

Name	Туре	Properties	Description
eClasses	config. EClassConfig	[0*]	
eDataTypes	config. EDataTypeConfig	[0*]	
eEnums	config.EEnumConfig	[0*]	

References

Name	Туре	Properties	Description
targetEPackage	ecore.EPackage	[01]	

Used at

• config.EcoreDocGeneratorConfig.ePackages

Class EReferenceConfig

Super-types

- config.AEReferenceConfig
- config.IDefaultValueConfig
- config.IENamedElementConfig
- config.IEReferenceConfig
- config.IEStructuralFeatureConfig

References

Name	Туре	Properties	Description
targetEReference	ecore.EReference	[01]	

Used at

• config.EClassConfig.eReferences

Class EcoreDocGeneratorConfig

Super-types

- config.IDefaultValueConfig
- config.IEAttributeConfig
- config.IEClassConfig
- config.IEClassifierConfig
- config.IEDataTypeConfig
- config.IEEnumConfig
- config.IEEnumLiteralConfig

- config.IENamedElementConfig
- config.IEPackageConfig
- config.IEReferenceConfig
- config.IEStructuralFeatureConfig

Attributes

Name	Туре	Properties	Description
documentTitle	EString	[01] Default: Ecore Documentation	

Containments

Name	Туре	Properties	Description
ePackages	config. EPackageConfig	[0*]	

Interface IDefaultValueConfig

Attributes

Name	Туре	Properties	Description
renderDefaults	EBoolean	[01] unsettable	

Interface IEAttributeConfig

Super-types

- config.IDefaultValueConfig
- config.IENamedElementConfig
- config.IEStructuralFeatureConfig

Interface IEClassConfig

Super-types

- config.IDefaultValueConfig
- config.IEClassifierConfig
- config.IENamedElementConfig

Attributes

Name	Туре	Properties	Description
renderSubTypes	EBoolean	[01] unsettable	Whether the list of sub-types should be rendered.
renderSuperTypes	EBoolean	[01] unsettable	Whether the list of super-types should be rendered.

Name	Туре	Properties	Description
repeatInherited	EBoolean	[01] unsettable	

Interface IEClassifierConfig

Super-types

- config.IDefaultValueConfig
- config.IENamedElementConfig

Attributes

Name	Туре	Properties	Description
renderUseCases	EBoolean	[01] unsettable	Whether use cases (references to other usages of this element) should be rendered.

Interface IEDataTypeConfig

Super-types

- config.IDefaultValueConfig
- config.IEClassifierConfig
- config.IENamedElementConfig

Interface IEEnumConfig

Super-types

- config.IDefaultValueConfig
- config.IEClassifierConfig
- config.IEDataTypeConfig
- config.IENamedElementConfig

Interface IEEnumLiteralConfig

Super-types

• config.IENamedElementConfig

Interface IENamedElementConfig

Attributes

Name	Туре	Properties	Description
render	EBoolean	[01] unsettable	Whether this element should be rendered at all.

Interface IEPackageConfig

Super-types

• config.IENamedElementConfig

Attributes

Name	Туре	Properties	Description
positionEClasses	EInt	[01] unsettable	Rendering position of all EClasses within an EPackage.
positionEDataTypes	EInt	[01] unsettable	Rendering position of all EDataTypes within an EPackage.
positionEEnums	EInt	[01] unsettable	Rendering position of all EEnums within an EPackage.

Interface IEReferenceConfig

Super-types

- config.IDefaultValueConfig
- config.IENamedElementConfig
- config.IEStructuralFeatureConfig

Interface IEStructuralFeatureConfig

Super-types

- config.IDefaultValueConfig
- config.IENamedElementConfig

Attributes

Name	Туре	Properties	Description
renderBounds	EBoolean	[01] unsettable	