CORNE / 42 KEYS

Your everyday keys

Caps Word for UPPER_CASE. Hyper for shortcuts. Hold a thumb for a layer.

HOST MODE **Hold Escape + Q = Mac** | **Hold Escape + W = Omarchy**

BASE / MAC UTILITIES

Quick term Cmd + `	Q	W	F	P	B		J	L	U	Y	'	Capture H: Clicks
Caps Word UPPER_CASE	A H: Cmd	R H: Alt	S H: Ctrl	T H: Shift	G		M	N H: Shift	E H: Ctrl	I H: Alt	O H: Cmd	Clipboard
Raycast H: Hyper	Z	X	C	D	V		K	H	,	.	/	Hyper Tap: 1-shot
			Escape H: System	Space H: Navigate	Tab H: Mouse		Enter H: Symbols	Backspace H: Numbers	Delete H: F-keys			

H = hold. Right bottom: tap, then a shortcut within 1.5 sec; or hold for normal Hyper.

Six outer keys - same purpose on both hosts

Position	Mac: left / right	Omarchy: left / right
Top	Quick terminal | Capture/Clicks	Scratchpad | Capture/Clicks
Middle	Caps Word | Clipboard	Caps Word | Clipboard
Bottom	Raycast/Hyper | Sticky Hyper	Menu/Super | Sticky Super

Hyper shortcuts - Mac

Hyper = left Ctrl + Alt + Shift + Cmd

Hyper +	Opens
A	ChatGPT
C	Claude
E	VS Code
L	Linear
T	Ghostty
W	cmux workspaces
B	Helium browser
V	Clipboard history
P	Bitwarden
M	IINA
O	Omarchy menu
K	Shortcut guide

Hold a thumb

Thumb	Layer
Escape	System
Space	Navigate
Tab	Mouse
Enter	Symbols
Backspace	Numbers
Delete	F-keys

Hold Escape + letter

Key	Mac	Omarchy
Q / W	Mac / Omarchy	Mac / Omarchy
F	Omarchy menu	Omarchy menu
P	Fullscreen capture	Record / stop
B	Capture menu	Screenshot OCR
J	Ghostty	Terminal
L	Helium	Browser
U	Shortcut guide	Keybindings
Y	Area capture	Screenshot

QUICK TERMINAL

Mac: Cmd + backtick (`).

Linux: Super + ` toggles the scratchpad.

Put a terminal there first: Super + Shift + `.

Flash the updated firmware first. Physical activation still needs testing.

The layers

Small labels show the Base key. Big labels show what it does while the thumb is held.

NAVIGATE — Hold Space

Mac shown; Linux editing follows host mode

Q Mission	W Prev desk	F Next desk	P -	B -	J Redo	L Paste	U Copy	Y Cut	' Undo
A Cmd	R Alt	S Ctrl	T Shift	G -	M Caps*	N Left	E Down	I Up	O Right
Z Hyper	X -	C -	D -	V -	K Insert	H Browser home	, Page down	. Page up	/ End

Right thumbs: Enter / Backspace / Delete. Linux: W/F = previous/next workspace; Q inactive.

MOUSE — Hold Tab

Mac shown; Linux editing follows host mode

Q -	W -	F -	P -	B -	J Redo	L Paste	U Copy	Y Cut	' Undo
A Cmd	R Alt	S Ctrl	T Shift	G -	M -	N Move left	E Move down	I Move up	O Move right
Z Hyper	X -	C -	D -	V -	K -	H Scroll left	, Scroll down	. Scroll up	/ Scroll right

Right thumbs: Right click / Left click / Middle click.

NUMBERS — Hold Backspace

Q [	W 7	F 8	P 9	B]	J -	L -	U -	Y -	' -
A ;	R 4	S 5	T 6	G =	M -	N Shift	E Ctrl	I Alt	O Cmd
Z `	X 1	C 2	D 3	V \	K -	H -	, -	. -	/ Hyper

Left thumbs: . / 0 / -

SYMBOLS — Hold Enter

Q {	W &	F *	P (	B }	J -	L -	U -	Y -	' -
A :	R $	S %	T ^	G +	M -	N Shift	E Ctrl	I Alt	O Cmd
Z ~	X !	C @	D #	V |	K -	H -	, -	. -	/ Hyper

Left thumbs: (/) / _

F-KEYS — Hold Delete

Q F12	W F7	F F8	P F9	B SysRq	J -	L -	U -	Y -	' -
A F11	R F4	S F5	T F6	G Scroll lock	M -	N Shift	E Ctrl	I Alt	O Cmd
Z F10	X F1	C F2	D F3	V Pause	K -	H -	, -	. -	/ Hyper

Left thumbs: Context menu / Space / Tab.

CLICKS

Hold outer top-right. Left thumbs: Middle / Left / Right click.
Right thumbs: Right / Left / Middle click. Clipboard shortcuts on both hands.

* Mac hidutil maps Caps Lock to Escape. Navigate H sends Browser Home, not a document Home key.
System: N/E/I = previous track / volume down / volume up; H/,/. = Bluetooth profiles 1/2/3; / clears current pairing.