CORNE / 42 KEYS

Your everyday keys

Caps Word for UPPER_CASE. Hyper for shortcuts. Hold a thumb for a layer.

HOST MODE **Hold Escape + Q = Mac** | **Hold Escape + W = Omarchy**

BASE / MAC UTILITIES

Quick term Cmd + `	Q	W	F	P	B		J	L	U	Y	'	Capture H: Clicks
Caps Word UPPER_CASE	A H: Cmd	R H: Alt	S H: Ctrl	T H: Shift	G		M	N H: Shift	E H: Ctrl	I H: Alt	O H: Cmd	Clipboard
Raycast H: Hyper	Z	X	C	D	V		K	H	,	.	/	Hyper Tap: 1-shot
			Escape H: System	Space H: Navigate	Tab H: Mouse		Enter H: Symbols	Backspace H: Numbers	Delete H: F-keys			

H = hold. Right bottom: tap, then a shortcut within 1.5 sec; or hold for normal Hyper.

Six outer keys - same purpose on both hosts

Position	Mac: left / right	Omarchy: left / right
Top	Quick terminal | Capture/Clicks	Scratchpad | Capture/Clicks
Middle	Caps Word | Clipboard	Caps Word | Clipboard
Bottom	Raycast/Hyper | Sticky Hyper	Menu/Super | Sticky Super

Hyper shortcuts - Mac

Hyper = left Ctrl + Alt + Shift + Cmd

Hyper +	Opens
A	ChatGPT
C	Claude
E	VS Code
L	Linear
T	Ghostty
W	cmux workspaces
B	Helium browser
V	Clipboard history
P	Bitwarden
M	IINA
O	Omarchy menu
K	Shortcut guide

Hold a thumb

Thumb	Layer
Escape	System
Space	Navigate
Tab	Mouse
Enter	Symbols
Backspace	Numbers
Delete	F-keys

Hold Escape + letter

Key	Mac	Omarchy
Q / W	Mac / Omarchy	Mac / Omarchy
F	Omarchy menu	Omarchy menu
P	Fullscreen capture	Record / stop
B	Capture menu	Screenshot OCR
J	Ghostty	Terminal
L	Helium	Browser
U	Shortcut guide	Keybindings
Y	Area capture	Screenshot

QUICK TERMINAL

Mac: Cmd + backtick (`).

Linux: Super + ` toggles the scratchpad.

Put a terminal there first: Super + Shift + `.

Flash the updated firmware first. Physical activation still needs testing.

The layers

Small labels show the Base key. Big labels show what it does while the thumb is held.

NAVIGATE — Hold Space

Mac shown; Linux editing follows host mode

Q	W	F	P	B	J	L	U	Y	'
Mission	Prev desk	Next desk	-	-	Redo	Paste	Copy	Cut	Undo
A	R	S	T	G	M	N	E	I	O
Cmd	Alt	Ctrl	Shift	-	Escape	Left	Down	Up	Right
Z	X	C	D	V	K	H	,	.	/
-	-	-	-	-	Insert	Home	Page down	Page up	End

Right thumbs: Enter / Backspace / Delete. Linux: W/F = previous/next workspace; Q inactive.

MOUSE — Hold Tab

Mac shown; Linux editing follows host mode

Q	W	F	P	B	J	L	U	Y	'
-	-	-	-	-	Redo	Paste	Copy	Cut	Undo
A	R	S	T	G	M	N	E	I	O
Cmd	Alt	Ctrl	Shift	-	-	Move left	Move down	Move up	Move right
Z	X	C	D	V	K	H	,	.	/
-	-	-	-	-	-	Scroll left	Scroll down	Scroll up	Scroll right

Right thumbs: Right click / Left click / Middle click.

NUMBERS — Hold Backspace

Q	W	F	P	B	J	L	U	Y	'
[	7	8	9	]	-	-	-	-	-
A	R	S	T	G	M	N	E	I	O
;	4	5	6	=	-	Shift	Ctrl	Alt	Cmd
Z	X	C	D	V	K	H	,	.	/
`	1	2	3	\	-	-	-	-	-

Left thumbs: . / 0 / -

SYMBOLS — Hold Enter

Q	W	F	P	B	J	L	U	Y	'
{	&	*	(	}	-	-	-	-	-
A	R	S	T	G	M	N	E	I	O
:	$	%	^	+	-	Shift	Ctrl	Alt	Cmd
Z	X	C	D	V	K	H	,	.	/
~	!	@	#	|	-	-	-	-	-

Left thumbs: (/) / _

F-KEYS — Hold Delete

Q	W	F	P	B	J	L	U	Y	'
F12	F7	F8	F9	SysRq	-	-	-	-	-
A	R	S	T	G	M	N	E	I	O
F11	F4	F5	F6	Scroll lock	-	Shift	Ctrl	Alt	Cmd
Z	X	C	D	V	K	H	,	.	/
F10	F1	F2	F3	Pause	-	-	-	-	-

Left thumbs: Context menu / Space / Tab.

CLICKS

Hold outer top-right. Left thumbs: Middle / Left / Right click.
Right thumbs: Right / Left / Middle click. Clipboard shortcuts on both hands.

Hyper is on the two bottom outer keys. Empty inner positions are disabled. Navigate M = Escape; H = Home.
System: N/E/I = previous track / volume down / volume up; H/,/. = Bluetooth profiles 1/2/3; / clears current pairing.