

E2E Networks Knowledgebase

Home > How to Install XRDP on CentOS and RedHat Linux 8/7

How to Install XRDP on CentOS and RedHat Linux 8/7

Introduction

Xrdp is an open-source and freely available Remote Desktop Protocol application which allows remote sessions of Linux Server from Windows machines. It will accept remote connections from rdesktop, freerdp and other remote desktop clients. This article guides, installation and configuration steps of xrdp on CentOS/RedHat Linux 8/7.

Step 1 : Update Server Node

```
# yum clean all
# yum -y update
```

After server update, Once restart the server node

```
# reboot
```

Step 2: Enable EPEL Repository

xrdp package is available on EPEL repository, so enable it to install on CentOS/RHEL Linux 8.

```
# yum install epel-release
```

Step 3: Install Desktop Environment (If it is not installed)

Install GUI (Graphical User Interface) with the following command if it is not installed.

```
# sudo yum groupinstall "Server with GUI"
```

Step 4: Install xrdp on CentOS/RHEL Linux 8/7

Following mention command to install xrdp applications

```
# yum install tigervnc-server xrdp
```

Step 5: Start/Enable and check the Status of xrdp.service

Once xrdp installation is done on the server node, start xrdp server with systemctl command

```
# sudo systemctl start xrdp.service
# sudo systemctl status xrdp.service
# sudo systemctl enable xrdp.service
```

Step 6: Check xrdp connection listening on port 3389 by default

xrdp is now listening on port 3389, check with following ss or netstat command below

```
# netstat -antp | grep xrdp
```

```
[root@localhost ~]# netstat -antp | grep xrdp
tcp        0      0 127.0.0.1:3350      0.0.0.0:*           LISTEN
2153/xrdp-sesman
tcp        0      0 0.0.0.0:3389        0.0.0.0:*           LISTEN
2154/xrdp
```

Step 7: Check the status of firewall service on the Server Node

```
# sudo systemctl status firewalld.service
```

In case of not in active state, run below command

```
# sudo systemctl enable firewalld.service
# sudo systemctl start firewalld.service
```

Add the following rule on Firewall (if the Firewall service is enabled).


```
# sudo firewall-cmd --permanent --add-port=3389/tcp
# sudo firewall-cmd --reload
```

At last, again reboot the Server Node via below command


```
# reboot
```

Step 7: Access RedHat/CentOS Linux 8/7 system using xrdp

Now, it's time to take RDP sessions from any Windows machine using Remote Desktop Protocol.



Below screen shows that we have successfully taken GUI sessions from Windows machine.



Updated on December 18, 2020