
Day 5: Review and Practice Practical Create a physical network topology in Cisco Packet Tracer. Task: Document the steps for configuring a small network.

Tasks:-

1. Open Cisco Packet Tracer and create a new project file named 'HomeWiFiNetwork.pkt' with three PCs and one wireless router connected appropriately.


Ans.:-

1. Open Cisco Packet Tracer.
2. Click File → New.
3. Click File → Save As and save the project as:
   HomeWiFiNetwork.pkt
4. From Network Devices → Wireless Devices, drag Wireless Router (WRT300N or Home Wireless Router) onto the workspace.
5. From End Devices, drag 3 PCs onto the workspace.
6. Connect the devices:
7. If using a home wireless router with Wi-Fi, you can leave the PCs as wireless (after adding wireless adapters if required) or connect them using Copper Straight-Through cables:
   a. PC0 → Router LAN Port 1
   b. PC1 → Router LAN Port 2
   c. PC2 → Router LAN Port 3
8. Wait for the link lights to turn green, indicating successful connections.
9. Save the project again (Ctrl + S).



2. Assign static IP addresses to each PC in your Packet Tracer network so they are on the same subnet (e.g., 192.168.10.x), and configure the default gateway to the router's IP.

Ans.:-



Step1 :- decide ip address :-

Device	IP Address	Subnet Mask	Default Gateway
Wireless Router (LAN)	192.168.10.1	255.255.255.0	—
PC0	192.168.10.2	255.255.255.0	192.168.10.1
PC1	192.168.10.3	255.255.255.0	192.168.10.1
PC2	192.168.10.4	255.255.255.0	192.168.10.1

Step 2:- Configure the router

1. Click the Wireless Router.
2. Go to GUI or Config (depending on the router model).
3. Set the LAN IP Address to:

a. IP Address: 192.168.10.1

b. Subnet Mask: 255.255.255.0

4. Save the configuration.

Step 3:-Configure each PC :-

For **PC0**:

1. Click PC0.
2. Select Desktop → IP Configuration.
3. Choose Static.
4. Enter:

- IP Address: 192.168.10.2
- Subnet Mask: 255.255.255.0
- Default Gateway: 192.168.10.1

Step4 :-For PC1:

- IP Address: 192.168.10.3
- Subnet Mask: 255.255.255.0
- Default Gateway: 192.168.10.1

Step5 :-**For PC2**:

- IP Address: 192.168.10.4
- Subnet Mask: 255.255.255.0
- Default Gateway: 192.168.10.1

Step6 :- Verify connectivity

1. On PC0-3
2. open Desktop
3. Command Prompt
4. Test pc :


ping 192.168.10.3

**3. Test connectivity by using the Packet Tracer 'ping' tool to verify that all PCs can communicate with each other and the router.


Hint: Use the Command Prompt tool on each PC and type 'ping [other PC's IP]'.**

Ans.:-


1. **Pc0 ping with pc1 & pc2:-**



2. **Pc1 ping with pc1 & pc2:-**




3. **Pc2 ping with Pc0 & Pc1 :-**




4. Document each step you took to build and configure your Packet Tracer network, including screenshots of your topology and the IP configuration windows for each PC, in a Word or PDF file.


Ans.:-




- **Router 0 configuration :-**




- **Pc0 join router0 network :-**




- **Pc1 join router0 network :-**




- **Pc2 join router0 network :-**



- **Router 1 configuration :-**



- **Pc3 join router1 network :-**



- **Pc4 join router1 network :-**

