NATIONAL UNIVERSITY OF COMPUTER & EMERGING SCIENCE Computer Networks Lab (CL3001) Lab Session 03


Packet Tracer - Creating a New Topology

What is Packet Tracer? Packet Tracer is a protocol simulator developed by Dennis Frezzo and his team at Cisco Systems. Packet Tracer (PT) is a powerful and dynamic tool that displays the various protocols used in networking, in either Real Time or Simulation mode. This includes layer 2 protocols such as Ethernet and PPP, layer 3 protocols such as IP, ICMP, and ARP, and layer 4 protocols such as TCP and UDP. Routing protocols can also be traced.

Purpose: The purpose of this lab is to become familiar with building topologies in Packet Tracer.

Requisite knowledge: This lab assumes some understanding of the Ethernet protocol. At this point we have not discussed other protocols, but will use Packet Tracer in later labs to discuss those as well.


Step 1: Start Packet Tracer



Step 2: Choosing Devices and Connections

We will begin building our network topology by selecting devices and the media in which to connect them. Several types of devices and network connections can be used. For this lab we will keep it simple by using **End Devices**, **Switches**, **Hubs**, and **Connections**.

Single click on each group of devices and connections to display the various choices. The devices you see may differ slightly.



Step 3: Building the Topology - Adding Hosts

Single click on the End Devices.



Single click on the Generic host.




Move the cursor into topology area. You will notice it turns into a plus "+" sign.



Single click in the topology area and it copies the device.





Add three more hosts.










Step 4: Building the Topology – Connecting the Hosts to Hubs and Switches Adding a Hub

Select a hub, by clicking once on **Hubs** and once on a **Generic** hub.



Add the hub by moving the plus sign "+" below PC0 and PC1 and click once.



Connect PC0 to Hub0 by first choosing Connections.




Click once on the Copper Straight-through cable.




Perform the following steps to connect **PC0** to **Hub0**:

- 1. Click once on PC0
- 2. Choose FastEthernet
- 3. Drag the cursor to **Hub0**
- 4. Click once on Hub0 and choose Port 0
- 5. Notice the green link lights on both the **PC0** Ethernet NIC and the **Hub0** Port 0 showing that the link is active.




Repeat the steps above for **PC1** connecting it to **Port 1** on **Hub0**. (The actual hub port you choose does not matter.)



Adding a Switch

Select a switch, by clicking once on **Switches** and once on a **2950-24** switch.



Add the switch by moving the plus sign "+" below PC2 and PC3 and click once.



Connect PC2 to Hub0 by first choosing Connections.




Click once on the Copper Straight-through cable.




Perform the following steps to connect PC2 to Switch0:

- 1. Click once on PC2
- 2. Choose FastEthernet
- 3. Drag the cursor to Switch0
- 4. Click once on Switch0 and choose FastEthernet0/1
- 5. Notice the green link lights on **PC2** Ethernet NIC and amber light **Switch0 FastEthernet0/1 port**. The switch port is temporarily not forwarding frames, while it goes through the stages for the Spanning Tree Protocol (STP) process.
- 6. After a about 30 seconds the amber light will change to green indicating that the port has entered the forwarding stage. Frames can now have forwarded out the switch port.


Note: Spanning Tree Protocol (STP) is discussed later.



Repeat the steps above for **PC3** connecting it to **Port 3** on **Switch0** on port **FastEtherent0/2**. (The actual switch port you choose does not matter.)




Move the cursor over the link light to view the port number. Fa means FastEthernet, 100 Mbps Ethernet.



Step 5: Configuring IP Addresses and Subnet Masks on the Hosts

Before we can communicate between the hosts we need to configure IP Addresses and Subnet Masks on the devices.


Click once on PC0.



Choose the **Config** tab and click on **Settings**. It is here that you can change the name of PC0. It is also here where you would enter a **Gateway** IP Address, also known as the default gateway and the **DNS Server** IP Address. We will discuss this later, but this would be the IP address of the local router. If you want, you can enter the Gateway IP Address 172.16.1.1 and DNS Server IP Address 172.16.1.100, although it will not be used in this lab.



Click on **Interface** and then **FastEthernet**. Although we have not yet discussed IP Addresses, add the IP Address to 172.16.1.10. Click once in the Subnet Mask field to enter the default Subnet Mask. You can leave this at 255.255.0.0. We will discuss this later.



Also, notice this is where you can change the Bandwidth (speed) and Duplex of the Ethernet NIC (Network Interface Card). The default is Auto (auto negotiation), which means the NIC will negotiate with the hub or switch. The bandwidth and/or duplex can be manually set by removing the check from the **Auto** box and choosing the specific option.

Bandwidth - Auto

If the host is connected to a hub or switch port which can do 100 Mbps, then the Ethernet NIC on the host will choose 100 Mbps (Fast Ethernet). Otherwise, if the hub or switch port can only do 10 Mbps, then the Ethernet NIC on the host will choose 10 Mbps (Ethernet).

Duplex - Auto

Hub: If the host is connected to a hub, then the Ethernet NIC on the host will choose Half Duplex.

Switch: If the host is connected to a switch, and the switch port is configured as Full Duplex (or Auto negotiation), then the Ethernet NIC on the host will choose Full Duplex. If the switch port is configured as Half Duplex, then the Ethernet NIC on the host will choose Half Duplex. (Full Duplex is a much more efficient option.)

The information is automatically saved when entered.

To close this dialog box, click the "X" in the upper right.




Repeat these steps for the other hosts. Use the information below for IP Addresses and Subnet Masks.

Host	IP Address	Subnet Mask
PC0	172.16.1.10	255.255.0.0
PC1	172.16.1.11	255.255.0.0
PC2	172.16.1.12	255.255.0.0
PC3	172.16.1.13	255.255.0.0

Verify the information

To verify the information that you entered, move the Select tool (arrow) over each host.




Deleting a Device or Link

To delete a device or link, choose the **Delete** tool and click on the item you wish to delete.




Step 6: Connecting Hub0 to Switch0


To connect like-devices, like a Hub and a Switch, we will use a Cross-over cable. Click once the **Cross-over** Cable from the **Connections** options.




Move the Connections cursor over **Hub0** and click once.




Select Port 5 (actual port does not matter).




Move the Connections cursor to Switch0.



Click once on Switch0 and choose FastEthernet0/4 (actual port does not matter).



The link light for switch port **FastEthernet0/4** will begin as amber and eventually change to green as the Spanning Tree Protocol transitions the port to forwarding.



Step 7: Verifying Connectivity in Realtime Mode


Be sure you are in Realtime mode.



Select the **Add Simple PDU** tool used to ping devices.



Click once on PC0, then once on PC3.



The PDU Last Status should show as Successful.




Resetting the Network

At this point we will want to reset the network, Whenever you want to reset the network and begin the simulation again, perform the following tasks:

Click **Delete** in the PDU area.




Now, Power Cycle Devices and confirm the action.



Waiting for Spanning Tree Protocol (STP)

Note: Because Packet Tracer also simulates the Spanning Tree Protocol (later), at times the switch may show amber lights on its interfaces. You will need to wait for the lights to turn green on the switches before they will forward any Ethernet frames.




Step 8: Verifying Connectivity in Simulation Mode

Be sure you are in **Simulation** mode.




Deselect all filters (All/None) and select only ICMP.




Select the Add Simple PDU tool used to ping devices..



Click once on PC0, then once on PC3.




Continue clicking **Capture/Forward** button until the ICMP ping is completed. You should see the ICMP messages move between the hosts, hub and switch. The PDU **Last Status** should show as **Successful**. Click on **Clear Event List** if you do not want to look at the events or click **Preview Previous Events** if you do. For this exercise it does not matter.




Step 9: Saving the Topology

Perform the following steps to save the topology (uses .pkt file extension).




Opening Existing Topologies




Тур


Opening Existing PT Topologies




Simulation modal of bus topology:



Simulation modal of star topology



Simulation modal of mesh topology:



Tasks:

- 1. Show the packet header format of ARP in Cisco Packet tracer.
- 2.Identify the differences between Switch and Hub.
- 3. Take two PCs, connect them and assign them an ip addresses and check their connectivity with the help of PING command. (Hint: Use Boson NetSim for this task.)
- 4.Take two PCs, connect them with suitable wire and also describe the reason of selection of wire. Assign them IP addresses and check their connectivity by using PING command. (Use Packet tracer for this task).
- 5. What are the main command modes? Compare them.
- 6.Test basic commands on your designed network?

7.Design and configure the network given in Figure-1 and check the connectivity by PING command. Also describe the functionality of devices in given scenario.




Figure-1