

Socio estratégico



Impulsan










Cobol - Clase 29

Comandos en línea (TSO)







Reglas de la clase



Micrófonos apagados



Consultas al final de la clase




Consultas por chat





Cronograma



Primera **Parte**

18:30 а 19:25

Break

19:25 19:35

Segunda **Parte**

19:35 20:30






¿Qué veremos hoy?

- Comandos básicos
- Manejo de archivos y librerías
- Práctica







TSO (**Time Sharing Option**) es un entorno interactivo que se utiliza comúnmente en sistemas mainframe para permitir a los usuarios interactuar con el sistema y ejecutar comandos. Es parte del sistema operativo z/OS de IBM





ISPF (Interactive System Productivity Facility) es una interfaz de usuario que proporciona un conjunto de utilidades interactivas para facilitar la gestión y desarrollo de aplicaciones en entornos mainframe.





```
CE DATA SET = SYS1.VTAM.SOURCE(USSN)
                         3333333
TERMINAL NAME = LCL703
                                   NETWORK-QUALIFIED NAME = P390.LCL703
                                   NETWORK-ID = P390
SSCPHAME = P390SSCP
         OS/390 APPLICATION SERVICES SYSTEM - RELEASE 2.10.0
          "LOGON" FOLLOWED BY THE TSO USERID. EXAMPLE "LOGON IBMUSER" OR
    ENTER L FOLLOWED BY THE APPLID
    EXAMPLES: "L TSO", "L CICS", "L IMS3270
  USER001_
```



Login

```
TSO/E LOGON -----
IKJ56714A Enter current password for USER001
   Enter LOGON parameters below:
                                                  RACF LOGON parameters:
   Userid
            ===> USER001
   Password ===>
                                                  New Password ===>
   Procedure ===> DBSPROC
                                                  Group Ident ===>
   Acct Nmbr ===> ACCT#
   Size
            ===> 4096
   Perform
            ===>
   Command ===> ISPF
   Enter an 'S' before each option desired below:
           -Nomail
                          -Nonotice
                                           -Reconnect
                                                             -OIDcard
PF1/PF13 ==> Help
                    PF3/PF15 ==> Logoff
                                           PA1 ==> Attention
                                                                PA2 ==> Reshow
```



ISPF

```
Menu Utilities Compilers options Status Help
                           ISPF Primary Option Menu
                                                                   End of data
Option ===>
  Settings
                 Terminal and user parameters
                                                         User ID . : USER001
   View
                Display source data or listings
                                                         Time. . . : 21:33
   Edit
                Create or change source data
                                                         Terminal: : 3278
   Utilities
                Perform utility functions
                                                         Screen. : 1
                Interactive language processing
   Foreground
                                                         Language: : ENGLISH
                 Submit job for language processing
   Batch
                                                         Appl ID . : ISR
                 Enter TSO or Workstation commands
   Command
                                                         TSO logon : ISPFPROC
  Dialog Test
                Perform dialog testing
                                                         TSO prefix:
                Library administrator functions
  LM Facility
                                                         System ID : P390
  IBM Products IBM program development products
                                                         MVS acct. : ACCT#
  SCLM
                 SW Configuration Library Manager
                                                         Release . : ISPF 5.0
                 ISPF Object/Action Workplace
  Workplace
                 Additional IBM Products
  More
     Enter X to Terminate using log/list defaults
 F1=Help
             F2=Split
                           F3=Exit
                                        F7=Backward F8=Forward
                                                                  F9=Swap
F10=Actions F12=Cancel
```




Teclas Function

```
Menu Utilities Compilers Options Status Help
                          ISPF Primary Option Menu
                                                                  End of data
Option ===>
  Settings
                 Terminal and user parameters
                                                        User ID . : USER001
                Display source data or listings
   View
                                                        Time : 21:33
  Edit
                Create or change source data
                                                        Terminal. : 3278
   Utilities
                Perform utility functions
                                                        Screen. : 1
  Foreground
                Interactive language processing
                                                        Language: : ENGLISH
                 Submit job for language processing
                                                        Appl ID . : ISR
   Batch
                 Enter ISO or Workstation commands
   Command
                                                        TSO logon : ISPFPROC
  Dialog Test
                Perform dialog testing
                                                        TSO prefix:
8 LM Facility
                Library administrator functions
                                                        System ID : P390
  IBM Products IBM program development products
                                                        MVS acct. : ACCT#
10 SCLM
                 SW Configuration Library Manager
                                                        Release . : ISPF 5.0
                 ISPF Object/Action Workplace
11 Workplace
  More
                 Additional IBM Products
    Enter X to Terminate using log/list defaults
                                       F7=Backward F8=Forward
 F1=Help
             F2=Split
                           F3=Exit
                                                                 F9=Swap
F10=Actions F12=Cancel
```





Teclas Function



F1 Help: Ayuda sobre la pantalla donde se encuentra

F7 y F8: Desplazamiento vertical de la pantalla

F2 Split : Divide la pantalla en dos

F9 Swap: Cambio de pantalla

F3 Exit: Sale de la pantalla actual y vuelve a la anterior

F10 y F11: Desplazamiento horizontal de la pantalla

F5 Find: Busca

F12 Cancel : Cancela la operación actual



1 View

Indicar la librería, el nombre del miembro es opcional.

Se se especifica lo abre en formato VIEW. Si no se indica lista todos los miembros de la librería.

Menu	RefList	R <u>e</u> fMode	<u>U</u> tilities	<u>W</u> orkstation	<u>H</u> elp	
			View	Entry Panel		
Command	===>					
					Мо	re: +
ISPF Li	_					
	ect .					
Grou	in	BASE		· · · _		_
Memb	er	CL11EJ03	(B)	ank or patter	rn for member selecti	on list)
Data	Set Name	d, Sequen		M Data Set:	ed)	
Worksta	tion File	:				
File	Name					
		_		Options		
Initial	Macro .			/ Confir	m Cancel/Move/Replac	е
Profile	Name			Browse	e Mode	
					on Workstation	
Data Se	t Passwor	d		/ Warn d	on First Data Change	
	p F2	=Split =Cancel	F3=Exit	F7=Backwa	ard F8=Forward F9=	Swap



1 View

También se puede acceder escribiendo el nombre de la librería, con y sin indicar el miembro y también se puede ingresar archivos.

Se se especifica lo abre en formato VIEW. Si no se indica lista todos los miembros de la librería.

<u>M</u> enu <u>R</u> efList R <u>e</u> fMode <u>U</u> tilit	ties <u>W</u> orkstation <u>H</u> elp
	/iew Entry Panel
Command ===>	
	More: +
ISPF Library:	
Project	
Group	
Туре	
Member	(Blank or pattern for member selection list)
Volume Serial	
Workstation File:	
File Name	
	Options
Initial Macro	/ Confirm Cancel/Move/Replace
Profile Name	Browse Mode
Format Name	
Data Set Password	Warn on First Data Change
F1=Help F2=Split F3=E>	kit F7=Backward F8=Forward F9=Swap



2 Edit

Se utiliza de igual manera que la opción 1 View, la diferencia es que la librería o archivo se mostrará en formato EDIT. Es decir se podrá editar.

<u>M</u> enu	RefList	R <u>e</u> fMode	<u>U</u> tilities !	_MF <u>W</u> orkstation	<u>H</u> elp
Command	===> <u> </u>		Edit E	ntry Panel	
Grou Type	ect				member selection list)
Data	Partitione Set Name Ime Serial			Data Set: not cataloged)	
	tion File Name				
Profile Format Data Se F1=Hel	Macro . Name Name Tasswor p F2	d :=Split		Mixed Mode Edit on Wor Preserve VE	ncel/Move/Replace rkstation 3 record length F8=Forward F9=Swap





3 Utilities

2 Crear, Renombrar, etc

3 Mover o Copiar

4 Listar

```
Menu Help
                           Utility Selection Panel
Option ===>
                                                                   More:
1 Library
               Compress or print data set. Print index listing.
                 rename, delete, browse, edit or view members
2 Data Set
               Allocate, rename, delete, catalog, uncatalog, or display
                 information of an entire data set
  Move/Copy
               Move, copy, or promote members or data sets
               Print or display (to process) list of data set names.
   Dslist
                 Print or display VIOC information
               Reset statistics for members of ISPF library
   Reset
               Initiate hardcopy output
   Hardcopy
   Transfer
               Download ISPF Client/Server or Transfer data set
   Outlist
               Display, delete, or print held job output
   Commands
               Create/change an application command table
               This option reserved for future expansion
  Reserved
11 Format
               Format definition for formatted data Edit/Browse
                                                             (Standard Dialog)
12 SuperC
               Compare data sets
13 SuperCE
               Compare data sets Extended
                                                             (Extended Dialog)
14 Search-For
               Search data sets for strings of data
                                                             (Standard Dialog)
 F1=Help
                           F3=Exit
                                        F7=Backward F8=Forward
              F2=Split
                                                                  F9=Swap
F10=Actions
            F12=Cancel
```





3.3 Move/Copy

C para Copiar **M** para Mover

Librería/Archivo origen

```
Menu RefList Utilities Help
                             Move/Copy Utility
Option ==
                                                                More:
 C Copy data set or member(s)
                                      CP Copy and print
                                      MP Move and print
 M Move data set or member(s)
 L Copy and LMF lock member(s)
                                      LP Copy, LMF lock, and print
   LMF Promote data set or member(s)
                                      PP LMF Promote and print
Specify "From" Data Set below, then press Enter key
From ISPF Library:
               (--- Options C, CP, L, and LP only ---)
   Project.
                                (Blank or pattern for member list,
                                 "*" for all members)
From Other Partition or Sequential Data Set:
   Data Set Name . . .
 F1=Help
             F2=Split
                          F3=Exit
                                      F7=Backward F8=Forward
                                                               F9=Swap
F10=Actions F12=Cancel
```





Indicar el destino

3.3 Move/Copy

```
Menu RefList Utilities Help
COPY
        From DM.BASE.JCL(CL11EJ03)
Command ===>
                                                           More:
Specify "To" Data Set Below
To ISPF Library:
   Project ____
                             Replace option:
                                Enter "/" to select option
                                  Replace like-named members
                       (Blank unless member is to be renamed)
To Other Partitioned or Sequential Data Set:
   Data Set Name . . .
                             (If not cataloged)
   Volume Serial . . .
Data Set Password . . (If password protected)
To Data Set Options:
   Sequential Disposition Pack Option SCLM Setting
 F1=Help
        F2=Split F3=Exit F7=Backward F8=Forward
                                                         F9=Swap
F10=Actions F12=Cancel
```





3.4 Dslist

Nombre de la librería a buscar


```
Menu RefList RefMode Utilities Help
                                                            End of data
                         Data Set List Utility
Option ===>
                            P Print data set list
  blank Display data set list
      V Display VTOC information
                                       PV Print VIOC information
Enter one or both of the parameters below:
  Dsname Level . . .
  Volume serial . .
Data set list options
  Initial View . . . 1 1. Volume Enter "/" to select option
                                        / Confirm Data Set Delete
                      2. Space
                      3. Attrib
                                           Confirm Member Delete
                      4. Total
When the data set list is displayed, enter either:
 "/" on the data set list command field for the command prompt pop-up,
 an ISPF line command, the name of a ISO command, CLISI, or REXX exec, or
 "=" to execute the previous command.
 F1=Help F2=Split F3=Exit
                                   F7=Backward F8=Forward
                                                         F9=Swap
F10=Actions F12=Cancel
```



Vistas

Indica si el miembro de una librería o el archivo que estamos visualizando esta en modo VIEW, EDIT, BROWSER.

```
File Edit Edit_Settings Menu Utilities Compilers Test Help
          DM.BASE.SRC(CL11EJ03) - 01.16
                                                    Columns 00001 00072
EDIT
Command ===>
                                                       Scroll ===> PAGE
      000100
            IDENTIFICATION DIVISION.
000110
            PROGRAM-ID. CL11EJ03.
            TITLE 'CLASE 11 - EJERCICIO 3'.
000111
000112
000113
            ENVIRONMENT DIVISION.
000114
            CONFIGURATION SECTION.
000115
            SPECIAL-NAMES.
000116
                DECIMAL-POINT IS COMMA.
000117
000118
            INPUT-OUTPUT SECTION.
000119
000120
            FILE-CONTROL.
000121
000122
                SELECT ENTRADA ASSIGN TO ENTRADA
000123
                           ORGANIZATION IS SEQUENTIAL
000124
                          ACCESS MODE
                                     IS SEQUENTIAL
000126
                           FILE STATUS IS FS-ENTRADA.
                        F3=Exit
F1=Help
            F2=Split
                                   F5=Rfind
                                               F6=Rchange
                                                           F7=Up
 F8=Do⊌n
            F9=Swap
                       F10=Left
                                   F11=Right
                                              F12=Cancel
```







Vista EDIT

Sobre la numeración de las líneas se puede ingresar distintos comandos:

I-Inserta un renglón en blanco

C-copia un renglón, indicar A after o B before donde es el destino

M-Mueve un registro , indicar **A** after o **B** before donde es el destino

D-Delete, elimina un registro

```
File Edit Edit_Settings Menu Utilities Compilers Test Help
EDIT
         DM.FILE.CL11EJ03.ENTRADA
                                                      Columns 00001 00072
                                                         Scroll ===> CSR
Command ===>
         000100 2023-01-0110100MCCARTNEY, BRANDA
                                                         ALMACEN
000200 2023-01-0110050EIFFEL, EMILIO
                                                         ALMACEN
000300 2023-01-0110050EIFFEL, EMILIO
                                                         ALMACEN
 0400 2023-01-0110045ANCHORENA, AMPARO
                                                         ALMACEN
6J0500 2023-01-0110050EIFFEL, EMILIO
                                                         ALMACEN
000600 2023-01-0110001BLANCO, FLORENCIA
                                                         ALMACEN
000700 2023-01-0110045ANCHORENA, AMPARO
                                                         ALMACEN
000800 2023-01-0110050EIFFEL, EMILIO
                                                         ALMACEN
000900 2023-01-0110100MCCARTNEY, BRANDA
                                                         ALMACEN
001000 2023-01-0110001BLANCO, FLORENCIA
      ******************************* Bottom of Data **************
F1=Help
            F2=Split
                        F3=Exit
                                    F5=Rfind
                                                F6=Rchange
                                                            F7=Up
```



SPOOL

M More: Additional IBM Products

5 SDSF: Spool Search and Display Facility

ST: Status of jobs

			ISPF Prima	ry Option Menu		
0p	tion ===> <u>H</u>					
0	Settings	Terminal	and user pa	rameters	User ID .	: USER001
1	View	Display	source data	or listings	Time	: 22:25
2	Edit	Create o	r change sou	rce data	Terminal.	: 3278
3	Utilities	Perform	utility func	tions	Screen	: 2
4	Foreground	Interact	ive language	processing	Language.	: ENGLISH
5	Batch	Submit j	ob for langu	age processing	Appl ID .	: ISR
6	Command	Enter TS	O or Worksta	tion commands	TSO logon	: ISPFPROC
7	Dialog Test	Perform	dialog testi	ng	TSO prefi	×:
8	LM Facility	Library	administrato	r functions	System ID	: P390
9	IBM Products	IBM proq	ram developm	ent products	MVS acct.	: ACCT#
10	SCLM	SW Confi	quration Lib	rary Manager	Release .	: ISPF 5.0
11	Workplace	ISPF Obj	ect/Action W	orkplace		
M	More	Addition	al IBM Produ	cts		
	Enter X to	Terminate	using log/l	ist defaults		
F	1=Help F2	2=Split	F3=Exit	F7=Backward	F8=Forward	F9=Swap
F1	0=Actions F12	?=Cancel				

```
IBM Products Panel
 Option ===> 5_
                                                                  More:
   SMP/E
               System Modification Program/Extended
   ISMF
               Integrated Storage Management Facility
   RACE
               Resource Access Control Facility
               Hardware Configuration Dialogs
   HCD
   SDSF
               Spool Search and Display Facility
   IPCS
               Interactive Problem Control System
   DITTO
               DITTO/ESA for MVS Version 1
   RMF
               Resource Measurement Facility
   DESORT
               Data Facility Sort
10 OMVS
               MVS OpenEdition
11 DB2PM
               Database Preformance Monitor
12 DB2DC
               Database data collection
13 DB2
               Data Base Products
14 RRS
               Resource Recovery Services
15 DB2ADM
               Data Base Admin Tool
16 QMF
               Query Management Facility
 F1=Help
              F2=Split
                           F3=Exit
                                       F7=Backward F8=Forward F9=Swap
F10=Actions F12=Cancel
```

```
Display Filter View Print Options Help
HQX7703 ----- SDSF PRIMARY OPTION MENU ------
COMMAND INPUT ===> ST_
                                                           SCROLL ===>
     Active users
                                      INII Initiators
      Input queue
                                           Printers
     Output queue
                                      PUN
                                           Punches
     Held output queue
                                           Readers
     Status of jobs
                                      LINE Lines
                                      NODE Nodes
     System log
                                           Spool offload
     Members in the MAS
      Job classes
                                      ULOG User session log
     Scheduling environments
     WLM resources
Licensed Materials - Property of IBM
5647-A01 (C) Copyright IBM Corp. 1981, 2000. All rights reserved.
US Government Users Restricted Rights - Use, duplication or
F1=HELP
             F2=SPLIT
                         F3=END
                                      F4=RETURN F5=IFIND
                                                              F6=BOOK
             F8=DOUN
                         F9=SUAP
                                     F10=LEFT
                                                             F12=RETRIEVE
                                                 F11=RIGHT
```





SPOOL

M More : Additional IBM Products

5 SDSF : Spool Search and Display Facility

ST: Status of jobs

Nombre del JOB (JCL), usuario o proceso en ejecución o finalizado OK o con Error

ID único que asigna el Mainframe a cada ejecución

```
Display Filter
                   View Print Options Help
SDSF STATUS DISPLAY ALL CLASSES
                                                          LINE 1-16 (74)
COMMAND INPUT ===> _
                                                                  SCROLL ===> F
     JOBNAME
               JobID
                        Owner
                                  Prty Queue
                                                   C Pos
                                                           SAff
                                                                  ASys Status
                                      EXECUTION
     PROF OP
               TSU02398 PR0F003
                                                                  SYS1
                                                           SYS1
     USERC d1
               TSU02402 USER001
                                       EXECUTION
                                                                  SYS1
                                                             SYS1
     SYSLOG
               STC02334 +MASTER+
                                       EXECUTION
     RACF
                                                                  SYS1
                                       EXECUTION
               STC02349 RACF
     NFSC
               STC02332 NFSC
                                       EXECUTION
                                                                  SYS1
     VTAM
               STC02331 VTAM
                                       EXECUTION
                                                           SYS1
                                                                  SYS1
     INII
               STC02333 INIT
                                       EXECUTION
                                                                  SYS1
     INIT
               STC02338 INIT
                                       EXECUTION
                                                                  SYS1
     INIT
               STC02337 INIT
                                       EXECUTION
                                                                 SYS1
     INIT
               STC02339 INIT
                                       EXECUTION
                                                                  SYS1
     INIT
               STC02336 INIT
                                       EXECUTION
                                                                  SYS1
                                                           SYS1
     INIT
               STC02335 INIT
                                       EXECUTION
                                                                  SYS1
     INIT
               STC02341 INIT
                                       EXECUTION
                                                                  SYS1
               STC02340 INIT
     INIT
                                       EXECUTION
                                                                 SYS1
     INIT
               STC02342 INIT
                                       EXECUTION
                                                                  SYS1
     INII
               STC02343 INIT
                                       EXECUTION
                                                                  SYS1
                                                           SYS1
 F1=HELP
               F2=SPLIT
                             F3=END
                                          F4=RETURN
                                                        F5=IFIND
                                                                      F6=B00K
 F7=UP
               F8=DOUN
                            F9=SWAP
                                         F10=LEFT
                                                       F11=RIGHT
```

Dueño de la ejecución






5 SDSF : Spool Search and Display Facility

ST: Status of jobs

SDSF	STATUS DI	CSPLAY ALL CL	ASSES			LINE 49-64	1 (74)
COMM	AND INPUT	===> _				SCI	ROLL ===> PAGI
NP	JOBNAME	Node Device	Max-RC	SrvClass	WPos	Scheduling-	-Env Dly Mo
	\$MASCOMM				0		
	NFSC	L	ABEND S222		0		
	NFSS	_	ABEND S222		0		
	SDCC	L	CC 0000		0		
	PORTMAP	L	CC 4095		0		
	TCPIP	L	CC 0000		0		
	HTTPD1	L	CC 0000		0		
	SYSLOG	L			0		
	TSO	L			0		
	CICSA	L	CC 0001		0		
	IRRDPTAB	L	CC 0000		0		
	NFSC	L	ABEND S222		0		
	SDSF	L	CC 0000		0		
	PORTMAP	L	CC 4095		0		
	NFSS	L	ABEND S222		0		
	TCPIP	L	CC 0000		0		
F1=	HELP	F2=SPLIT	F3=END	F4=RETUR		5=IFIND	F6=B00K
F7=		F8=DOWN	F9=SWAP	F10=LEFT		L1=RIGHT	F12=RETRIEVE







5 SDSF : Spool Search and Display Facility

26

ST: Status of jobs

Display Filter View Print Options Help SDSF STATUS DISPLAY ALL CLASSES DATA SET DISPLAYED COMMAND INPUT ===> SCROLL ===> JobID JOBNAME Prty Queue Pos SAff Owner ASys Status IBMUSER TSU02320 IBMUSER 1 PRINT 17 HTTPD1 STC02325 WEBSRV 1 PRINT 18 SYSLOG STC02278 +MASTER+ 1 PRINT 19 STC02312 +++++++ TSO 1 PRINT 20 CICSA STC02321 CICSA 1 PRINT 21 IRRDPTAB STC02369 IRRDPTAB 1 PRINT 22 TSU02382 PR0F003 23 PROF003 1 PRINT 24 JCLPRB01 J0B02399 PR0F003 1 PRINT Ĥ JCLPRB01 J0B02400 PR0F003 1 PRINT A 25

1 PRINT

JCLPRB01 J0B02401 PR0F003

F1=HELP F2=SPLIT F3=END F4=RETURN F5=IFIND F6=BOOK F7=UP F8=DOWN F9=SWAP F10=LEFT F11=RIGHT F12=RETRIEVE



Muestra el JCL tal cual se ejecutó



5 SDSF : Spool Search and Display Facility

ST: Status of jobs

Muestra la información de la ejecución todo junto en un sola vista



IBMUSI HTTPD: SYSLOI TSO CICSA IRRDPI PROFOI	1 STC02325 G STC02278 STC02312	WEBSRV +MASTER+	1	PRINT PRINT		17	SAFF	ASys Status
HTTPD: SYSLOI TSO CICSA IRRDPI PROFOI	1 STC02325 G STC02278 STC02312	WEBSRV +MASTER+	1	PRINT				
SYSLOO TSO CICSA IRRDP PROFOO	G STC02278 STC02312	+MASTER+				10		
TSO CICSA IRRDP PROFO	STC02312		1			18		
CICSA IRRDP PROFO		+++++++		PRINT		19		
IRRDP	STC02321		1	PRINT		20		
PROFO	OICOLOLI	CICSA	1	PRINT		21		
	TAB STC02369	IRRDPTAB	1	PRINT		22		
	03 TSU02382	PROF003	1	PRINT		23		
JCLPRI	B01 J0B02399	PROF003	1	PRINT	A	24		
JCLPRI	B01 J0B02400	PROF003	1	PRINT	A	25		
JCLPRI	B01 J0B02401	PROF003	1	PRINT	A	26		
F1=HELP F7=UP	F2=SPLIT F8=DOWN	F3=E1		F4=RE F10=LE			=IFIND =RIGHT	





5 SDSF : Spool Search and Display Facility

ST: Status of jobs

Muestra la información de la ejecución todo junto en un sola vista



	STATUS DI		CLASSES					DATA	SET DISPLAYED SCROLL ===> PAG
NP			Owner	Prty	Queue	C	Pos	SAFF	ASys Status
	IBMUSER	TSU02320	IBMUSER	1	PRINT		17		
	HTTPD1	STC02325	WEBSRY	1	PRINT		18		
	SYSLOG	STC02278	+MASTER+	1	PRINT		19		
	TSO	STC02312	+++++++	1	PRINT		20		
	CICSA	STC02321	CICSA	1	PRINT		21		
	IRRDPTAB	STC02369	IRRDPTAB	1	PRINT		22		
	PROF003	TSU02382	PROF003	1	PRINT		23		
5	JCLPRB01	J0B02399	PROF003	1	PRINT	A	24		
	JCLPRB01	J0B02400	PROF003	1	PRINT	A	25		
	JCLPRB01	J0B02401	PROF003	1	PRINT	A	26		
F1:	HELP	F2=SPLIT	F3=EN	D	F4=RE	TURN	F5:	=IFIND	F6=B00K
F7:	:UP	F8=DOUN	F9=SW	AP	F10=LE	FT	F11:	-RIGHT	F12=RETRIEVE






SPOOL

M More : Additional IBM Products

5 SDSF : Spool Search and Display Facility

ST: Status of jobs



Otros comandos

C: Cancela la ejecución de un JCL en curso

P: Purga una ejecución, es decir la elimina del spool

OWNER {usuarios}: Se puede filtrar para ver solo las ejecución de un usuarios, y con **OWNER *** volver a ver todas las ejecuciones

```
SDSF STATUS DISPLAY ALL CLASSES
COMMAND INPUT ===> OWNER USEROO1
NP JOBNAME Node Device Max-RC
PROFOO1 L
```

PRE {valor}: Se puede filtrar para ver solo las ejecución con dicho prefijo, y con **PRE *** volver a ver todas las ejecuciones

```
SDSF STATUS DISPLAY ALL CLASSES

COMMAND INPUT ===> PRE COMP*

NP JOBNAME JobID Owner Prty Que

PROF001 TSU02403 PROF001 15 EXI
```





1: SPUFI

Q: QMF

M More : Additional IBM Products

13 DB2 : Data Base Products

			DB2I PRIM	ARY OPTION ME	NU S	SID: DSN1			
COM	MAND ===>								
Sel	ect one of	the following	ng DB2 funct	ions and press	ENTER.				
			-						
1	SPUFI		(Process S	QL statements)				
2	DCLGEN		(Generate	(Generate SQL and source language declarations)					
3 PROGRAM PREPARATION			(Prepare a	(Prepare a DB2 application program to run)					
4	PRECOMPIL	Ε	(Invoke DB2 precompiler)						
5 BIND/REBIND/FREE			(BIND, REBIND, or FREE plans or packages)						
6	RUN		(RUN an SQL program)						
7	DB2 COMMA	NDS	(Issue DB2 commands)						
8	UTILITIES		(Invoke DB2 utilities)						
D	DB2I DEFA	ULTS	(Set global parameters)						
Q	QMF		(Query Mar	agement Facili	ity				
X	EXIT		(Leave DB2	?I)					
	=HELP	F2=SPLIT	F3=END	F4=RETURN F10=LEFT	F5=RFIND	F6=RCHANGE			
F7	=UP	F8=DOWN	F9=SWAP	F11=RIGHT	F12=RETRIEVE				



Logout

Menu Utilities Compilers Options Status Help ISPF Primary Option Menu Option ===

Desde la pantalla inicial del ISPF seleccionar la opción X


```
Sectings
                 Terminal and user parameters
                                                         User ID . : USER001
  View
                Display source data or listings
                                                         Time. . . : 22:51
  Edit
                Create or change source data
                                                         Terminal: 3278
  Utilities
                Perform utility functions
                                                         Screen. : 3
  Foreground
                Interactive language processing
                                                         Language: : ENGLISH
  Batch
                Submit job for language processing
                                                         Appl ID . : ISR
                Enter ISO or Workstation commands
                                                         TSO logon : ISPFPROC
  Command
  Dialog Test
                Perform dialog testing
                                                         TSO prefix:
                Library administrator functions
  LM Facility
                                                         System ID : P390
  IBM Products IBM program development products
                                                         MVS acct. : ACCT#
10 SCLM
                 SW Configuration Library Manager
                                                         Release . : ISPF 5.0
1 Workplace
                 ISPF Object/Action Workplace
                 Additional IBM Products
   More
    Enter X to Terminate using log/list defaults
F1=Help
             F2=Split
                           F3=Exit
                                        F7=Backward F8=Forward
                                                                  F9=Swap
            F12=Cancel
F10=Actions
```



Logout

Sp	ecify Disposition of Log Data Set	
Command ===>		
	More:	d
Log Data Set (USEROO1.9	SPFLOG1.LIST) Disposition:	
Process Option	1. Print data set and delete	
	2. Delete data set without printing	
	3. Keep data set - Same	
	(allocate same data set in next session)	
	4. Keep data set - New	
	(allocate new data set in next session)	
Batch SYSOUT class		
Local printer ID or		
writer-name		
Local SYSOUT class		
20041 313031 21433		
List Data Set Options r	ont available	
cist bata set options i	iot avaitable	
Press ENTER key to comp	lete ISPE termination	
enter env command to re	eturn to the primary option menu.	
***	Co. (Decision for contract contract)	
	ion: (Required for system printer)	
===>	E3-Evit E7-Rackward E8-Enruard E9-Suan	

Logout (logoff)



```
NETWORK-QUALIFIED NAME = P390.LCL701
                                 NETWORK-ID = P390
       OS/390 APPLICATION SERVICES SYSTEM - RELEASE 2.10.0
=> ENTER "LOGON" FOLLOWED BY THE TSO USERID. EXAMPLE "LOGON IBMUSER" OR
==> EXAMPLES: "L TSO", "L CICS", "L IMS3270
```





COMMAND



- START: Vuelve a la pantalla inicial del ISPF
- HI COBOL: Muestra la sintaxis COBOL con colores
- HI JCL: Muestra la sintaxis JCL con colores
- HI AUTO: Detecta automáticamente la sintaxis COBOL o JCL para mostrarla con colores
- SCRNAME: Permite asignarle un nombre a una pantalla en el SWAP LIST
- KEYS: Permite editar las funciones asignadas a cada tecla Fn función.
- SWAP LIST: Lista las pantallas activas (máximo 8)
- SUBMIT / SUB: Ejecuta un JCL







Comunicación

Foro de consultas TEC:

https://campus.soysilvertech.org

Mails de consulta TEC:

consultasCOBOL@soysilvertech.org



Sivertech +talento +tecnología +empleabilidad