Bugs Report

Status:	Backlog	Backlog						
Project:	OpenCart	OpenCart						
Components:	None	None						
Affects versions:	Front Store	Front Store						
Fix versions:	Front Store	Front Store						
	-							
Type:	Bug		Priority:	Highest				
Reporter:	Anca Pintilie		Assignee:	Anca Pintili				
Resolution:	Unresolved		Votes:	0				
Labels:	None							
Remaining Estimate:	Not Specified							
Time Spent:	Not Specified							
Original estimate:	Not Specified							
Attachments:	☐ 1pWeight.png ☐ 2	pWeight.png						
Issue links:								
issue illiks.	Relates relates to	OP-39	Verify changing the weight of the Pro					
	relates to	OP-27	Shopping Cart Functionality					
Epic Link:	Shopping Cart Module							

- Open the Application URL in any supported browser: https://demo.opencart.com
 One product is already in the shopping cart (1 iMac)

- Suspis.

 1. Go to "Shopping Cart" page

 2. Change the quantity from 1 product to 2 products into the "Quantity" field of the Product in the displayed Shopping Cart page

 3. Click on "Update" icon option

Expected results:
The weight of both products should be updated automatically when changing the quantity of the products. Correct weight of the two products should be displayed in the Shopping Cart page

Actual results:
The weight of both products is not updated automatically when changing the quantity of the products. A wrong weight is displayed in the Shopping Cart page.

Status:	Backlog	Backlog							
Project:	OpenCart								
Components:	None	None							
Affects versions:	Admin	Admin							
Fix versions:	Admin	Admin							
Type:	Bug	Bug		Priority:	Highest				
Reporter:	Anca Pintilie			Assignee:	Anca Pintili				
Resolution:	Unresolved	Unresolved			0				
Labels:	None	None							
Remaining Estimate:	Not Specified	Not Specified							
Time Spent:	Not Specified	Not Specified							
Original estimate:	Not Specified								
Environment:	MacOs, Safari, https://d	MacOs, Safari, https://demo.opencart.com/admin/index.php?route=catalog/product form&user_token=e23d4511fd15754ad4de8c89699b5bdb							
Attachments:		☐ ProductTagMessage.png							
Issue links:	Relates								
	relates to	OP-22	Verify the automatic me	essage is displ					
	relates to	OP-2	As Admin I want to be	As Admin I want to be able to add/edi					
Epic Link:	Admin Products Modul	e							

Preconditions: Admin is logged in with valid username and password

- Steps:

 1. Go to Catalog Products

 2. Cilick "Add New" button from the upper right corner

 3. A new window is opened (13 Tabs)

 4. Go to "General" tab

 5. Write at least two words using "space" key between them in "Product Tag" field (Example: open cart project final)

 6. Fill in all the mandatory fields from all the tabs

 7. Cilick "Save"

Expected results:
The new product can not be saved and the message "Comma separated" that is written under the Product Tag field shows up like a warning message (Ex: the text colour changes to red).

Actual Results:

The new product can not be saved and the message "Comma separated" that is written under the Product Tag field doesn't shows up like a warning message (Ex: the text colour changes to red). Nothing happens

[OP-16] The category (in the top menu of	every page) will be displayed	when the "Top" checkbox	is not selected Created: 29/May	y/23 Updated: 20/Oct/23				
Status:	Backlog	Backlog						
Project:	OpenCart	OpenCart						
Components:	None	None						
Affects versions:	Admin	Admin						
Fix versions:	Admin	Admin						
Type:	Bug	Bug			Medium			
Reporter:	Anca Pintilie			Assignee:	Anca Pintilio			
Resolution:	Unresolved			Votes:	0			
Labels:	None	None						
Remaining Estimate:	Not Specified	Not Specified						
Time Spent:	Not Specified	Not Specified						
Original estimate:	Not Specified	Not Specified						
Environment:	MacOS, Safari, https://d	MacOS, Safari, https://demo.opencart.com						
Issue links:	Relates							
	relates to	OP-15	Verify not selecting the "Top" checkb					
	relates to	OP-5 As Admin I want to be able to add/del						
	relates to	01-0	7 to 7 to 1111111 T Walle to be					

- Admin successfully logged in with valid username and password Steps:

- Steps:

 1. Go to Catalog Category in the administration

 2. Click "Insert" button in the upper right corner

 3. You will be directed to the category's information page

 4. Fill in all the mandatory category information under three tabs: "General", "Data", "Design". (Data Top checkbox is not selected)

 5. Click "Save" button in the upper right corner

 6. Check the top menu of every page to see if the new category will not be displayed

Expected results:

Not selecting the "Top" checkbox will NOT DISPLAY this category in the top menu of every page. Actual results:
Not selecting the "Top" checkbox will still DISPLAY this category in the top menu of every page