ROLLUPOS APPLICATION USER MANUAL • ADMIN & DEV TOOLS

🛰️ Gravity Agent Monitor

Real-Time Multi-Workstation Antigravity Telemetry, Trajectory Reader & Live 2-Way AgentAPI Dispatch

Version: v1.4.0 | Build Hash: #7e3ba534 | 👑 Admin-Only Cartridge | Auto-Synced: 2026-10-26 23:32

🆕 **What Changed in This Build:** Auto-detected new interactive controls in v1.4.0: 🧠 Auto, ⚡ Flash Lite, 🚀 Flash, 💎 Pro, 🚀

1. ⚡ 60-Second Quickstart Guide

1. **Verify Workstation Connection**
   Sign into RollupOS as Admin and launch Gravity Agent Monitor. The app automatically unlocks via your Admin session and connects to your primary LAN sidecar (`192.168.86.47:8765`) or Tailscale mesh node.

2. **Monitor Live Conversations (Pulse Tab)**
   Check the live status indicators on every active desktop conversation: spinning rings indicate active tool execution, bouncing badges signal unread completions, and amber alerts highlight steps awaiting user approval.

3. **Inspect Full Step-by-Step Trajectories**
   Tap any conversation card on the Pulse tab to jump into Trajectory view—read full user/agent messages, expand collapsible reasoning/tool blocks, and preview generated Markdown artifacts in the slide-up sheet.

4. **Reply or Launch New Tasks Remotely**
   Type directly into the bottom composer inside Trajectory view to reply to a live session, or open the Ops & Launcher tab (`⚙️ Nodes`) to start a brand-new conversation in any project workspace with 1-tap Skill injection.

2. 🧭 Screen-by-Screen & Navigation Map

SCREEN / TAB / MODAL	WHAT IT CONTROLS & HOW TO USE IT
📡 **Pulse (Sidebar Replica)**	Mirrors your desktop Antigravity conversation list across active PCs with unread/running status badges and Auxiliary Overview rollup.
📜 **Trajectory**	Full chronological transcript viewer with tool-call inspection, artifact preview modal, and live 2-way reply bar.
🗄️ **Vault / Artifacts**	Browse recent Markdown plans, reports, and generated workspace deliverables without remoting into your PC.
⚙️ **Ops & Launcher (`Nodes`)**	CPU/RAM host vitals, Multi-PC 'Follow-Me' fleet configuration, Keep-Awake toggle, and new project/skill task dispatcher.

3. 🔬 In-Depth Feature Guide & Workflows

Multi-PC 'Follow-Me' Dynamic Fleet

Add both your Home PC and Office PC (via LAN IP or `100.x.y.z` Tailscale IP) under Ops & Launcher. Gravity polls all configured nodes in parallel and automatically highlights whichever workstation is actively executing turns.

Direct 2-Way AgentAPI Prompt & Skill Dispatch

Uses your workstation's authenticated `X-Gravity-Token` header to dispatch replies into an existing conversation or spin up a new chat scoped to any registered project (`FF_2026`, `Div2`, `CSC Skills`, etc.) with optional pre-populated skill prompts.

Coffee / WakeLock Mode for Unattended Builds

Tap `☕ Toggle Keep-Awake` in Ops & Launcher to hold an Android screen WakeLock while monitoring long `/goal` builds or deployments.

4. ⚙️ Settings, Secret Vault & Multi-User Data Isolation

SETTING KEY	FIELD DESCRIPTION	TYPE	DEFAULT
`primary_workstation_url`	Primary Workstation Sidecar URL (HTTPS Tunnel or LAN)	`text`	`https://unexpected-computing-director-atmosphere.trycloudflare.com`
`tailscale_workstation_url`	Secondary / Tailscale Workstation URL (Optional)	`text`	`http://192.168.86.47:8765`
`sidecar_token`	X-Gravity-Token Shared Secret	`text`	`csc-gravity-admin-2026-x9f4k2`

🔒 **Storage Namespace Pattern:** `rollup::v1::u::<google-email>::app::gravity-agent-monitor::*`

📦 **Active App Storage Keys:** `__user_config__` (Managed automatically)

🔐 **Private On-Device Vault Secrets:** `GRAVITY_SIDECAR_TOKEN`

Isolated Per-User Storage (RollupBridge) | Screen WakeLock Keep-Awake | Encrypted On-Device Secret Vault

5. 🎛️ Live UI Controls Reference & Recent Updates

Interactive Controls Detected in Current Build (`v1.4.0`):

🔐 Unlock with Passkey | 🧿 Awake: OFF | 🔒 | 🌐 All PCs (Auto Follow-Me) | 🧠 Auto | ⚡ Flash Lite | 🚀 Flash | 💎 Pro | 🚀 | ← | ↻ Sync | 📋 | ✅ Approve & Proceed | 📄 Export PDF

Pro Tips & Best Practices:

- When away from home Wi-Fi, paste your Tailscale IP (`http://100.x.y.z:8765`) in Ops -> Multi-PC Fleet for seamless 5G remote steering.
- Tap any artifact link inside a trajectory step to open the formatted Artifact Preview bottom sheet without leaving the chat.

Recent Cartridge Update Log (Auto-Tracked on Publish):

- `49441bd` (2026-10-26) — feat(gravity): sync HTTPS tunnel & mobile UX to GitHub Pages (2026-10-26 22:34)
- `fb38d7c` (2026-10-26) — feat(gravity): sync HTTPS tunnel & mobile UX to GitHub Pages (2026-10-26 22:33)
- `9a2de8d` (2026-10-26) — feat(gravity): sync HTTPS tunnel & mobile UX to GitHub Pages (2026-10-26 22:17)
- `4610b5b` (2026-10-26) — feat(gravity): sync HTTPS tunnel & mobile UX to GitHub Pages (2026-10-26 20:01)
- `b55e402` (2026-10-26) — feat(gravity): sync HTTPS tunnel & mobile UX to GitHub Pages (2026-10-26 16:42)

RollupOS Automated Documentation Engine • Cartridge ID: `gravity-agent-monitor`

Canonical PDF: `manuals/gravity-agent-monitor_User_Manual.pdf`