# TCP Congestion Control -- Overview

Kameswari Chebrolu


Seminal Paper: Congestion Avoidance and Control by Van Jacobson and Michael J. Karels

## **Recap: TCP Services**


- Multiplexing/Demultiplexing
- Reliable point-to-point data transfer
- Full-duplex
- Congestion control
- Flow control

Sliding window Protocol

# **Recap: Sliding Window**




#### **Congestion Control: Problem Statement**



- Many flows pass through a router; number varies with time
- Flows can be TCP or UDP
- The link capacities of the routers are different
- End Result: Throughput achieved by a given flow function of many factors

# **Congestion Control: Challenge**




- Need to estimate (W) (of sliding window) such that each flow gets its fair share
- Estimate small → underutilization; Estimate large → Congestion
- W will vary over time
- Congestion Control: Preventing sources from sending too much data too fast and thereby 'congest' the network

#### **Sliding Window Protocol**

- Roughly, idea translates to the following:
- View network as a pipe
- Determine the capacity of the pipe (Bandwidth-delay product)
- Fill the pipe with data
- As you remove one packet form the pipe, add another
  - ACKs help clock out data (Self Clocking)

# **Self- Clocking**





- ONW = BXRTT
- 2 Max Thr A & B 7 = B
- Rati @ which Acks one coming?


  —> Rati @ which Pht

  Ly Link Capacity

Sel-docking







Quendo

- $\underline{W} > \underline{BDP} (in bits)$
- Sliding Window says
  - Thr = W/RTT >Bottleneck bandwidth
- Self-clocking says
  - Max thr is bottleneck
     bandwidth



P2


P3







#### **Window Size**



## Same Idea

- View network as a pipe
- Estimate Bandwidth-delay product (capacity) dynamically
- Uses the variable Congestion Window (CW) to track it
- Self Clocking: Captures bottleneck bandwidth
  - Use ACKs to clock out data
    - Not perfect (With competing traffic ack spacing will not be preserved)

# 3 Steps

- Getting to Equilibrium
- Conservation at equilibrium
  - Don't put new packet unless old one is removed
- Adapting to Path Dynamics

#### Summary

- Congestion Control is a complex problem
- Need to implement it in the context of the sliding window protocol
  - Self clocking is a useful feature (we will rely on this to capture bottleneck bandwidth)
  - Need to determine and adapt W (window size) such that you don't underutilize bandwidth or congest the network
- Ahead: Actual details