## **NAME**

virkeycode-osx - Key code values for osx

## **DESCRIPTION**

List of osx key code values, with corresponding osx key code names

• 0 (0x0)

Key name ANSI\_A

• 1 (0x1)

Key name ANSI\_S

• 2 (0x2)

Key name ANSI\_D

• 3 (0x3)

Key name ANSI\_F

• 4 (0x4)

Key name ANSI\_H

• 5 (0x5)

Key name ANSI\_G

• 6 (0x6)

Key name ANSI\_Z

• 7 (0x7)

Key name ANSI\_X

• 8 (0x8)

Key name ANSI\_C

• 9 (0x9)

Key name ANSI\_V

• 10 (0xa)

Key name ISO\_Section

• 11 (0xb)

Key name ANSI\_B

• 12 (0xc)

Key name ANSI\_Q

• 13 (0xd)

Key name ANSI\_W

• 14 (0xe)

Key name ANSI\_E

• 15 (0xf)

Key name ANSI\_R

• 16 (0x10)

Key name ANSI\_Y

• 17 (0x11)

Key name ANSI\_T

• 18 (0x12)

Key name ANSI\_1

• 19 (0x13)

Key name ANSI\_2

• 20 (0x14)

Key name ANSI\_3

• 21 (0x15)

Key name ANSI\_4

• 22 (0x16)

Key name ANSI\_6

• 23 (0x17)

Key name ANSI\_5

• 24 (0x18)

Key name ANSI\_Equal

• 25 (0x19)

Key name ANSI\_9

• 26 (0x1a)

Key name ANSI\_7

• 27 (0x1b)

Key name ANSI\_Minus

• 28 (0x1c)

Key name ANSI\_8

• 29 (0x1d)

Key name ANSI\_0

• 30 (0x1e)

Key name ANSI\_RightBracket

• 31 (0x1f)

Key name ANSI\_O

• 32 (0x20)

Key name ANSI\_U

• 33 (0x21)

Key name ANSI\_LeftBracket

• 34 (0x22)

Key name ANSI\_I

• 35 (0x23)

Key name ANSI\_P

• 36 (0x24)

Key name Return

• 37 (0x25)

Key name ANSI\_L

• 38 (0x26)

Key name ANSI\_J

• 39 (0x27)

Key name ANSI\_Quote

• 40 (0x28)

Key name ANSI\_K

• 41 (0x29)

Key name ANSI\_Semicolon

• 42 (0x2a)

Key name ANSI\_Backslash

• 43 (0x2b)

Key name ANSI\_Comma

• 44 (0x2c)

Key name ANSI\_Slash

• 45 (0x2d)

Key name ANSI\_N

• 46 (0x2e)

Key name ANSI\_M

• 47 (0x2f)

Key name ANSI\_Period

• 48 (0x30)

Key name Tab

• 49 (0x31)

Key name Space

• 50 (0x32)

Key name ANSI\_Grave

• 51 (0x33)

Key name Delete

• 53 (0x35)

Key name Escape

• 54 (0x36)

Key name RightCommand

• 55 (0x37)

Key name Command

• 56 (0x38)

Key name Shift

• 57 (0x39)

Key name CapsLock

• 58 (0x3a)

Key name Option

• 59 (0x3b)

Key name Control

• 60 (0x3c)

Key name RightShift

• 61 (0x3d)

Key name RightOption

• 62 (0x3e)

Key name RightControl

• 63 (0x3f)

Key name Function

• 64 (0x40)

Key name F17

• 65 (0x41)

Key name ANSI\_KeypadDecimal

• 67 (0x43)

Key name ANSI\_KeypadMultiply

• 69 (0x45)

Key name ANSI\_KeypadPlus

• 71 (0x47)

Key name ANSI\_KeypadClear

• 72 (0x48)

Key name VolumeUp

• 73 (0x49)

Key name VolumeDown

• 74 (0x4a)

Key name Mute

• 75 (0x4b)

Key name ANSI\_KeypadDivide

• 76 (0x4c)

Key name ANSI\_KeypadEnter

• 78 (0x4e)

Key name ANSI\_KeypadMinus

• 79 (0x4f)

Key name F18

• 80 (0x50)

Key name F19

• 81 (0x51)

Key name ANSI\_KeypadEquals

• 82 (0x52)

Key name ANSI\_Keypad0

• 83 (0x53)

Key name ANSI\_Keypad1

• 84 (0x54)

Key name ANSI\_Keypad2

• 85 (0x55)

Key name ANSI\_Keypad3

• 86 (0x56)

Key name ANSI\_Keypad4

• 87 (0x57)

Key name ANSI\_Keypad5

• 88 (0x58)

Key name ANSI\_Keypad6

• 89 (0x59)

Key name ANSI\_Keypad7

• 90 (0x5a)

Key name F20

• 91 (0x5b)

Key name ANSI\_Keypad8

• 92 (0x5c)

Key name ANSI\_Keypad9

• 93 (0x5d)

Key name JIS\_Yen

• 95 (0x5f)

Key name JIS\_KeypadComma

• 96 (0x60)

Key name F5

• 97 (0x61)

Key name F6

• 98 (0x62)

Key name F7

• 99 (0x63)

Key name F3

• 100 (0x64)

Key name F8

• 101 (0x65)

Key name F9

• 103 (0x67)

Key name F11

• 104 (0x68)

Key name JIS\_Kana

• 105 (0x69)

Key name F13

• 106 (0x6a)

Key name F16

• 107 (0x6b)

Key name F14

• 109 (0x6d)

Key name F10

• 110 (0x6e)

Key name unnamed

• 111 (0x6f)

Key name F12

• 113 (0x71)

Key name F15

• 114 (0x72)

Key name Help

• 115 (0x73)

Key name Home

• 116 (0x74)

Key name PageUp

• 117 (0x75)

Key name ForwardDelete

• 118 (0x76)

Key name F4

• 119 (0x77)

Key name End

• 120 (0x78)

Key name F2

• 121 (0x79)

Key name PageDown

• 122 (0x7a)

Key name F1

• 123 (0x7b)

Key name LeftArrow

• 124 (0x7c)

Key name RightArrow

• 125 (0x7d)

Key name DownArrow

• 126 (0x7e)

Key name UpArrow

• 255 (0xff)

Key name unnamed