## **NAME**

virkeycode-usb - Key code values for usb

## **DESCRIPTION**

List of usb key code values, with corresponding linux key code names

• 4 (0x4)

Key name KEY\_A

• 5 (0x5)

Key name KEY\_B

• 6 (0x6)

Key name KEY\_C

• 7 (0x7)

Key name KEY\_D

• 8 (0x8)

Key name KEY\_E

• 9 (0x9)

Key name KEY\_F

• 10 (0xa)

Key name KEY\_G

• 11 (0xb)

Key name KEY\_H

• 12 (0xc)

Key name KEY\_I

• 13 (0xd)

Key name KEY\_J

• 14 (0xe)

Key name KEY\_K

• 15 (0xf)

Key name KEY\_L

• 16 (0x10)

Key name KEY\_M

• 17 (0x11)

Key name KEY\_N

• 18 (0x12)

Key name KEY\_O

• 19 (0x13)

Key name KEY\_P

• 20 (0x14)

Key name KEY\_Q

• 21 (0x15)

Key name KEY\_R

• 22 (0x16)

Key name KEY\_S

• 23 (0x17)

Key name KEY\_T

• 24 (0x18)

Key name KEY\_U

• 25 (0x19)

Key name KEY\_V

• 26 (0x1a)

Key name KEY\_W

• 27 (0x1b)

Key name KEY\_X

• 28 (0x1c)

Key name KEY\_Y

• 29 (0x1d)

Key name KEY\_Z

• 30 (0x1e)

Key name KEY\_1

• 31 (0x1f)

Key name KEY\_2

• 32 (0x20)

Key name KEY\_3

• 33 (0x21)

Key name KEY\_4

• 34 (0x22)

```
Key name KEY_5
```

• 35 (0x23)

Key name KEY\_6

• 36 (0x24)

Key name KEY\_7

• 37 (0x25)

Key name KEY\_8

• 38 (0x26)

Key name KEY\_9

• 39 (0x27)

Key name KEY\_0

• 40 (0x28)

Key name KEY\_ENTER

• 41 (0x29)

Key name KEY\_ESC

• 42 (0x2a)

Key name KEY\_BACKSPACE

• 43 (0x2b)

Key name KEY\_TAB

• 44 (0x2c)

Key name KEY\_SPACE

• 45 (0x2d)

Key name KEY\_MINUS

• 46 (0x2e)

Key name KEY\_EQUAL

• 47 (0x2f)

Key name KEY\_LEFTBRACE

• 48 (0x30)

Key name KEY\_RIGHTBRACE

• 49 (0x31)

Key name KEY\_BACKSLASH

• 50 (0x32)

Key name KEY\_BACKSLASH

• 51 (0x33)

Key name KEY\_SEMICOLON

• 52 (0x34)

Key name KEY\_APOSTROPHE

• 53 (0x35)

Key name KEY\_GRAVE

• 54 (0x36)

Key name KEY\_COMMA

• 55 (0x37)

Key name KEY\_DOT

• 56 (0x38)

Key name KEY\_SLASH

• 57 (0x39)

Key name KEY\_CAPSLOCK

• 58 (0x3a)

Key name KEY\_F1

• 59 (0x3b)

Key name KEY\_F2

• 60 (0x3c)

Key name KEY\_F3

• 61 (0x3d)

Key name KEY\_F4

• 62 (0x3e)

Key name KEY\_F5

• 63 (0x3f)

Key name KEY\_F6

• 64 (0x40)

Key name KEY\_F7

• 65 (0x41)

Key name KEY\_F8

• 66 (0x42)

Key name KEY\_F9

• 67 (0x43)

Key name KEY\_F10

• 68 (0x44)

Key name KEY\_F11

• 69 (0x45)

Key name KEY\_F12

• 70 (0x46)

Key name KEY\_SYSRQ

• 71 (0x47)

Key name KEY\_SCROLLLOCK

• 72 (0x48)

Key name KEY\_PAUSE

• 73 (0x49)

Key name KEY\_INSERT

• 74 (0x4a)

Key name KEY\_HOME

• 75 (0x4b)

Key name KEY\_PAGEUP

• 76 (0x4c)

Key name KEY\_DELETE

• 77 (0x4d)

Key name KEY\_END

• 78 (0x4e)

Key name KEY\_PAGEDOWN

• 79 (0x4f)

Key name KEY\_RIGHT

• 80 (0x50)

Key name KEY\_LEFT

• 81 (0x51)

Key name KEY\_DOWN

• 82 (0x52)

Key name KEY\_UP

• 83 (0x53)

Key name KEY\_NUMLOCK

• 84 (0x54)

Key name KEY\_KPSLASH

• 85 (0x55)

Key name KEY\_KPASTERISK

• 86 (0x56)

Key name KEY\_KPMINUS

• 87 (0x57)

Key name KEY\_KPPLUS

• 88 (0x58)

Key name KEY\_KPENTER

• 89 (0x59)

Key name KEY\_KP1

• 90 (0x5a)

Key name KEY\_KP2

• 91 (0x5b)

Key name KEY\_KP3

• 92 (0x5c)

Key name KEY\_KP4

• 93 (0x5d)

Key name KEY\_KP5

• 94 (0x5e)

Key name KEY\_KP6

• 95 (0x5f)

Key name KEY\_KP7

• 96 (0x60)

Key name KEY\_KP8

• 97 (0x61)

Key name KEY\_KP9

• 98 (0x62)

Key name KEY\_KP0

• 99 (0x63)

Key name KEY\_KPDOT

• 100 (0x64)

Key name KEY\_102ND

• 101 (0x65)

Key name KEY\_COMPOSE

• 102 (0x66)

Key name KEY\_POWER

• 103 (0x67)

Key name KEY\_KPEQUAL

• 104 (0x68)

Key name KEY\_F13

• 105 (0x69)

Key name KEY\_F14

• 106 (0x6a)

Key name KEY\_F15

• 107 (0x6b)

Key name KEY\_F16

• 108 (0x6c)

Key name KEY\_F17

• 109 (0x6d)

Key name KEY\_F18

• 110 (0x6e)

Key name KEY\_F19

• 111 (0x6f)

Key name KEY\_F20

• 112 (0x70)

Key name KEY\_F21

• 113 (0x71)

Key name KEY\_F22

• 114 (0x72)

Key name KEY\_F23

• 115 (0x73)

Key name KEY\_F24

• 116 (0x74)

Key name KEY\_OPEN

• 117 (0x75)

Key name KEY\_HELP

• 118 (0x76)

Key name KEY\_MENU

• 119 (0x77)

Key name KEY\_FRONT

• 120 (0x78)

Key name KEY\_STOP

• 121 (0x79)

Key name KEY\_AGAIN

• 122 (0x7a)

Key name KEY\_UNDO

• 123 (0x7b)

Key name KEY\_CUT

• 124 (0x7c)

Key name KEY\_COPY

• 125 (0x7d)

Key name KEY\_PASTE

• 126 (0x7e)

Key name KEY\_FIND

• 127 (0x7f)

Key name KEY\_MUTE

• 128 (0x80)

Key name KEY\_VOLUMEUP

• 129 (0x81)

Key name KEY\_VOLUMEDOWN

• 133 (0x85)

• 135 (0x87)

Key name KEY\_RO

• 136 (0x88)

Key name KEY\_KATAKANAHIRAGANA

• 137 (0x89)

Key name KEY\_YEN

• 138 (0x8a)

Key name KEY\_HENKAN

• 139 (0x8b)

Key name KEY\_MUHENKAN

• 140 (0x8c)

Key name KEY\_KPJPCOMMA

• 144 (0x90)

Key name KEY\_HANGEUL

• 145 (0x91)

Key name KEY\_HANJA

• 146 (0x92)

Key name KEY\_KATAKANA

• 147 (0x93)

Key name KEY\_HIRAGANA

• 148 (0x94)

Key name KEY\_ZENKAKUHANKAKU

• 182 (0xb6)

Key name KEY\_KPLEFTPAREN

• 183 (0xb7)

Key name KEY\_KPRIGHTPAREN

• 224 (0xe0)

Key name KEY\_LEFTCTRL

• 225 (0xe1)

Key name KEY\_LEFTSHIFT

• 226 (0xe2)

• 227 (0xe3)

Key name KEY\_LEFTMETA

• 228 (0xe4)

Key name KEY\_RIGHTCTRL

• 229 (0xe5)

Key name KEY\_RIGHTSHIFT

• 230 (0xe6)

Key name KEY\_RIGHTALT

• 231 (0xe7)

Key name KEY\_RIGHTMETA

• 232 (0xe8)

Key name KEY\_PLAYPAUSE

• 233 (0xe9)

Key name KEY\_STOPCD

• 234 (0xea)

Key name KEY\_PREVIOUSSONG

• 235 (0xeb)

Key name KEY\_NEXTSONG

• 236 (0xec)

Key name KEY\_EJECTCD

• 237 (0xed)

Key name KEY\_VOLUMEUP

• 238 (0xee)

Key name KEY\_VOLUMEDOWN

• 239 (0xef)

Key name KEY\_MUTE

• 240 (0xf0)

Key name KEY\_WWW

• 241 (0xf1)

Key name KEY\_BACK

• 242 (0xf2)

Key name KEY\_FORWARD

• 243 (0xf3)

Key name KEY\_STOP

• 244 (0xf4)

Key name KEY\_FIND

• 245 (0xf5)

Key name KEY\_SCROLLUP

• 246 (0xf6)

Key name KEY\_SCROLLDOWN

• 247 (0xf7)

Key name KEY\_EDIT

• 248 (0xf8)

Key name KEY\_SLEEP

• 249 (0xf9)

Key name KEY\_SCREENLOCK

• 250 (0xfa)

Key name KEY\_REFRESH

• 251 (0xfb)

Key name KEY\_CALC