NAME

virkeycode-atset1 - Key code values for atset1

DESCRIPTION

List of atset1 key code values, with corresponding linux key code names

• 1 (0x1)

Key name KEY_ESC

• 2 (0x2)

Key name KEY_1

• 3 (0x3)

Key name KEY_2

• 4 (0x4)

Key name KEY_3

• 5 (0x5)

Key name KEY_4

• 6 (0x6)

Key name KEY_5

• 7 (0x7)

Key name KEY_6

• 8 (0x8)

Key name KEY_7

• 9 (0x9)

Key name KEY_8

• 10 (0xa)

Key name KEY_9

• 11 (0xb)

Key name KEY_0

• 12 (0xc)

Key name KEY_MINUS

• 13 (0xd)

Key name KEY_EQUAL

• 14 (0xe)

Key name KEY_BACKSPACE

• 15 (0xf)

```
Key name KEY_TAB
```

• 16 (0x10)

Key name KEY_Q

• 17 (0x11)

Key name KEY_W

• 18 (0x12)

Key name KEY_E

• 19 (0x13)

Key name KEY_R

• 20 (0x14)

Key name KEY_T

• 21 (0x15)

Key name KEY_Y

• 22 (0x16)

Key name KEY_U

• 23 (0x17)

Key name KEY_I

• 24 (0x18)

Key name KEY_O

• 25 (0x19)

Key name KEY_P

• 26 (0x1a)

Key name KEY_LEFTBRACE

• 27 (0x1b)

Key name KEY_RIGHTBRACE

• 28 (0x1c)

Key name KEY_ENTER

• 29 (0x1d)

Key name KEY_LEFTCTRL

• 30 (0x1e)

Key name KEY_A

• 31 (0x1f)

Key name KEY_S

• 32 (0x20)

Key name KEY_D

• 33 (0x21)

Key name KEY_F

• 34 (0x22)

Key name KEY_G

• 35 (0x23)

Key name KEY_H

• 36 (0x24)

Key name KEY_J

• 37 (0x25)

Key name KEY_K

• 38 (0x26)

Key name KEY_L

• 39 (0x27)

Key name KEY_SEMICOLON

• 40 (0x28)

Key name KEY_APOSTROPHE

• 41 (0x29)

Key name KEY_GRAVE

• 42 (0x2a)

Key name KEY_LEFTSHIFT

• 43 (0x2b)

Key name KEY_BACKSLASH

• 44 (0x2c)

Key name KEY_Z

• 45 (0x2d)

Key name KEY_X

• 46 (0x2e)

Key name KEY_C

• 47 (0x2f)

Key name KEY_V

• 48 (0x30)

Key name KEY_B

• 49 (0x31)

Key name KEY_N

• 50 (0x32)

Key name KEY_M

• 51 (0x33)

Key name KEY_COMMA

• 52 (0x34)

Key name KEY_DOT

• 53 (0x35)

Key name KEY_SLASH

• 54 (0x36)

Key name KEY_RIGHTSHIFT

• 55 (0x37)

Key name KEY_KPASTERISK

• 56 (0x38)

Key name KEY_LEFTALT

• 57 (0x39)

Key name KEY_SPACE

• 58 (0x3a)

Key name KEY_CAPSLOCK

• 59 (0x3b)

Key name KEY_F1

• 60 (0x3c)

Key name KEY_F2

• 61 (0x3d)

Key name KEY_F3

• 62 (0x3e)

Key name KEY_F4

• 63 (0x3f)

Key name KEY_F5

• 64 (0x40)

Key name KEY_F6

• 65 (0x41)

Key name KEY_F7

• 66 (0x42)

Key name KEY_F8

• 67 (0x43)

Key name KEY_F9

• 68 (0x44)

Key name KEY_F10

• 69 (0x45)

Key name KEY_NUMLOCK

• 70 (0x46)

Key name KEY_SCROLLLOCK

• 71 (0x47)

Key name KEY_KP7

• 72 (0x48)

Key name KEY_KP8

• 73 (0x49)

Key name KEY_KP9

• 74 (0x4a)

Key name KEY_KPMINUS

• 75 (0x4b)

Key name KEY_KP4

• 76 (0x4c)

Key name KEY_KP5

• 77 (0x4d)

Key name KEY_KP6

• 78 (0x4e)

Key name KEY_KPPLUS

• 79 (0x4f)

Key name KEY_KP1

• 80 (0x50)

Key name KEY_KP2

• 81 (0x51)

Key name KEY_KP3

• 82 (0x52)

Key name KEY_KP0

• 83 (0x53)

Key name KEY_KPDOT

• 84 (0x54)

Key name KEY_SYSRQ

• 85 (0x55)

Key name KEY_F16

• 86 (0x56)

Key name KEY_102ND

• 87 (0x57)

Key name KEY_F11

• 88 (0x58)

Key name KEY_F12

• 89 (0x59)

Key name KEY_KPEQUAL

• 90 (0x5a)

Key name KEY_F20

• 91 (0x5b)

Key name KEY_LINEFEED

• 92 (0x5c)

Key name KEY_KPJPCOMMA

• 93 (0x5d)

Key name KEY_F13

• 94 (0x5e)

Key name KEY_F14

• 95 (0x5f)

Key name KEY_F15

• 99 (0x63)

Key name KEY_PHONE

• 100 (0x64)

Key name KEY_OPEN

• 101 (0x65)

Key name KEY_PASTE

• 102 (0x66)

Key name KEY_SETUP

• 103 (0x67)

Key name KEY_FILE

• 104 (0x68)

Key name KEY_SENDFILE

• 105 (0x69)

Key name KEY_DELETEFILE

• 106 (0x6a)

Key name KEY_MSDOS

• 107 (0x6b)

Key name KEY_DIRECTION

• 108 (0x6c)

Key name KEY_EJECTCD

• 109 (0x6d)

Key name KEY_F23

• 111 (0x6f)

Key name KEY_F24

• 112 (0x70)

Key name KEY_KATAKANAHIRAGANA

• 113 (0x71)

Key name KEY_EXIT

• 114 (0x72)

Key name KEY_MOVE

• 115 (0x73)

Key name KEY_RO

• 116 (0x74)

Key name KEY_F21

• 117 (0x75)

Key name KEY_SCROLLUP

• 118 (0x76)

Key name KEY_ZENKAKUHANKAKU

• 119 (0x77)

Key name KEY_HIRAGANA

• 120 (0x78)

Key name KEY_KATAKANA

• 121 (0x79)

Key name KEY_HENKAN

• 123 (0x7b)

Key name KEY_MUHENKAN

• 125 (0x7d)

Key name KEY_YEN

• 126 (0x7e)

Key name KEY_KPCOMMA

• 57345 (0xe001)

Key name KEY_CONFIG

• 57346 (0xe002)

Key name KEY_WWW

• 57347 (0xe003)

Key name KEY_F17

• 57348 (0xe004)

Key name KEY_F19

• 57349 (0xe005)

Key name KEY_AGAIN

• 57350 (0xe006)

Key name KEY_PROPS

• 57351 (0xe007)

Key name KEY_UNDO

• 57352 (0xe008)

Key name KEY_EDIT

• 57353 (0xe009)

Key name KEY_NEW

• 57354 (0xe00a)

Key name KEY_REDO

• 57355 (0xe00b)

Key name KEY_SCALE

• 57356 (0xe00c)

Key name KEY_FRONT

• 57357 (0xe00d)

Key name KEY_HANJA

• 57358 (0xe00e)

Key name KEY_FORWARDMAIL

• 57359 (0xe00f)

Key name KEY_SCROLLDOWN

• 57360 (0xe010)

Key name KEY_PREVIOUSSONG

• 57362 (0xe012)

Key name KEY_SCREENLOCK

• 57363 (0xe013)

Key name KEY_XFER

• 57364 (0xe014)

Key name KEY_ALTERASE

• 57365 (0xe015)

Key name unnamed

• 57366 (0xe016)

Key name unnamed

• 57367 (0xe017)

Key name KEY_PROG2

• 57368 (0xe018)

Key name KEY_REWIND

• 57369 (0xe019)

Key name KEY_NEXTSONG

• 57370 (0xe01a)

Key name unnamed

• 57371 (0xe01b)

Key name unnamed

• 57372 (0xe01c)

Key name KEY_KPENTER

• 57373 (0xe01d)

Key name KEY_RIGHTCTRL

• 57374 (0xe01e)

Key name KEY_MENU

• 57375 (0xe01f)

Key name KEY_PROG1

• 57376 (0xe020)

Key name KEY_MUTE

• 57377 (0xe021)

Key name KEY_CALC

• 57378 (0xe022)

Key name KEY_PLAYPAUSE

• 57379 (0xe023)

Key name KEY_CLOSECD

• 57380 (0xe024)

Key name KEY_STOPCD

• 57381 (0xe025)

Key name KEY_SUSPEND

• 57382 (0xe026)

Key name KEY_CYCLEWINDOWS

• 57383 (0xe027)

Key name unnamed

• 57384 (0xe028)

Key name KEY_PLAYCD

• 57385 (0xe029)

Key name KEY_PAUSECD

• 57387 (0xe02b)

Key name KEY_PROG3

• 57388 (0xe02c)

Key name KEY_PROG4

• 57389 (0xe02d)

Key name KEY_DASHBOARD

• 57390 (0xe02e)

Key name KEY_VOLUMEDOWN

• 57391 (0xe02f)

Key name KEY_CLOSE

• 57392 (0xe030)

Key name KEY_VOLUMEUP

• 57393 (0xe031)

Key name KEY_RECORD

• 57394 (0xe032)

Key name KEY_HOMEPAGE

• 57395 (0xe033)

Key name KEY_PLAY

• 57396 (0xe034)

Key name KEY_FASTFORWARD

• 57397 (0xe035)

Key name KEY_KPSLASH

• 57398 (0xe036)

Key name KEY_BASSBOOST

• 57400 (0xe038)

Key name KEY_RIGHTALT

• 57401 (0xe039)

Key name KEY_PRINT

• 57402 (0xe03a)

Key name KEY_HP

• 57403 (0xe03b)

Key name KEY_CAMERA

• 57404 (0xe03c)

Key name KEY_CUT

• 57405 (0xe03d)

Key name KEY_SOUND

• 57406 (0xe03e)

Key name KEY_QUESTION

• 57407 (0xe03f)

Key name KEY_EMAIL

• 57408 (0xe040)

Key name KEY_CHAT

• 57409 (0xe041)

Key name KEY_FIND

• 57410 (0xe042)

Key name KEY_CONNECT

• 57411 (0xe043)

Key name KEY_FINANCE

• 57412 (0xe044)

Key name KEY_SPORT

• 57413 (0xe045)

Key name KEY_SHOP

• 57414 (0xe046)

Key name KEY_PAUSE

• 57415 (0xe047)

Key name KEY_HOME

• 57416 (0xe048)

Key name KEY_UP

• 57417 (0xe049)

Key name KEY_PAGEUP

• 57418 (0xe04a)

Key name KEY_CANCEL

• 57419 (0xe04b)

Key name KEY_LEFT

• 57420 (0xe04c)

Key name KEY_BRIGHTNESSDOWN

• 57421 (0xe04d)

Key name KEY_RIGHT

• 57422 (0xe04e)

Key name KEY_KPPLUSMINUS

• 57423 (0xe04f)

Key name KEY_END

• 57424 (0xe050)

Key name KEY_DOWN

• 57425 (0xe051)

Key name KEY_PAGEDOWN

• 57426 (0xe052)

Key name KEY_INSERT

• 57427 (0xe053)

Key name KEY_DELETE

• 57428 (0xe054)

Key name KEY_BRIGHTNESSUP

• 57429 (0xe055)

Key name KEY_SAVE

• 57430 (0xe056)

Key name KEY_SWITCHVIDEOMODE

• 57431 (0xe057)

Key name KEY_KBDILLUMTOGGLE

• 57432 (0xe058)

Key name KEY_KBDILLUMDOWN

• 57433 (0xe059)

Key name KEY_KBDILLUMUP

• 57434 (0xe05a)

Key name KEY_SEND

• 57435 (0xe05b)

Key name KEY_LEFTMETA

• 57436 (0xe05c)

Key name KEY_RIGHTMETA

• 57437 (0xe05d)

Key name KEY_COMPOSE

• 57438 (0xe05e)

Key name KEY_POWER

• 57439 (0xe05f)

Key name KEY_SLEEP

• 57443 (0xe063)

Key name KEY_WAKEUP

• 57444 (0xe064)

Key name KEY_REPLY

• 57445 (0xe065)

Key name KEY_SEARCH

• 57446 (0xe066)

Key name KEY_BOOKMARKS

• 57447 (0xe067)

Key name KEY_REFRESH

• 57448 (0xe068)

Key name KEY_STOP

• 57449 (0xe069)

Key name KEY_FORWARD

• 57450 (0xe06a)

Key name KEY_BACK

• 57451 (0xe06b)

Key name KEY_COMPUTER

• 57452 (0xe06c)

Key name KEY_MAIL

• 57453 (0xe06d)

Key name KEY_MEDIA

• 57455 (0xe06f)

Key name KEY_MACRO

• 57456 (0xe070)

Key name KEY_DOCUMENTS

• 57457 (0xe071)

Key name KEY_BATTERY

• 57458 (0xe072)

Key name KEY_BLUETOOTH

• 57459 (0xe073)

Key name KEY_WLAN

• 57460 (0xe074)

Key name KEY_UWB

• 57461 (0xe075)

Key name KEY_HELP

• 57462 (0xe076)

Key name KEY_KPLEFTPAREN

• 57463 (0xe077)

Key name KEY_F18

• 57464 (0xe078)

Key name KEY_COPY

• 57465 (0xe079)

Key name KEY_F22

• 57467 (0xe07b)

Key name KEY_KPRIGHTPAREN

• 57469 (0xe07d)

Key name KEY_EJECTCLOSECD