NAME
       bt−adapter – a bluetooth adapter manager

SYNOPSIS
       bt-adapter [OPTION...]

       Help Options:
        −h, −−help

       Application Options:
        −l, −−list
        −a, −−adapter=<name|mac>
        −i, −−info
        −d, −−discover
        −−set <property> <value>

DESCRIPTION
       This utility is used to manage Bluetooth adapters. You can list all available adapters, show information
       about adapter, change adapter properties or discover remote devices.

OPTIONS
       −h, −−help
          Show help

       −l, −−list
          List all available adapters

       −a, −−adapter <name|mac>
          Specify adapter to use by his Name or MAC address
          (if this option does not defined – default adapter used)

       −i, −−info
          Show information about adapter (returns all properties)

       −d, −−discover
          Discover remote devices (with remote device name resolving)

       −−set <property> <value>
          Change adapter properties (see ADAPTER PROPERTIES section for list
          of available properties)

ADAPTER PROPERTIES
       string Address [ro]
             The Bluetooth adapter address (MAC).

       string Alias [rw]
             The Bluetooth adapter friendly name.

       uint32 Class [ro]
             The Bluetooth class of device.

       boolean Powered [rw]
             Switch an adapter on or off. This will also set the
             appropiate connectable state.

       boolean Discoverable [rw]
             Switch an adapter to discoverable or non-discoverable
             to either make it visible or hide it.

                   If the DiscoverableTimeout is set to a non−zero
                   value then the system will set this value back to
                   false after the timer expired.

                   In case the adapter is switched off, setting this

```
                        value will fail.
```

boolean Pairable [rw]
    Switch an adapter to pairable or non-pairable.

```
                        Note that this property only affects incoming pairing
                        requests.
```

uint32 PaireableTimeout [rw]
    The pairable timeout in seconds. A value of zero
    means that the timeout is disabled and it will stay in
    pareable mode forever.

uint32 DiscoverableTimeout [rw]
    The discoverable timeout in seconds. A value of zero
    means that the timeout is disabled and it will stay in
    discoverable/limited mode forever.

```
                        The default value for the discoverable timeout should
                        be 180 seconds (3 minutes).
```

boolean Discovering [ro]
    Indicates that a device discovery procedure is active.

list   UUIDs [ro]
    List of 128−bit UUIDs that represents the available local
    services.

AUTHOR
    Alexander Orlenko <zxteam@gmail.com>.

SEE ALSO
    bt−agent (1) *bt−device* (1) *bt−network* (1)