NAME

virkeycode-atset2 - Key code values for atset2

DESCRIPTION

List of atset2 key code values, with corresponding linux key code names

• 1 (0x1)

Key name KEY_F9

• 3 (0x3)

Key name KEY_F5

• 4 (0x4)

Key name KEY_F3

• 5 (0x5)

Key name KEY_F1

• 6 (0x6)

Key name KEY_F2

• 7 (0x7)

Key name KEY_F12

• 9 (0x9)

Key name KEY_F10

• 10 (0xa)

Key name KEY_F8

• 11 (0xb)

Key name KEY_F6

• 12 (0xc)

Key name KEY_F4

• 13 (0xd)

Key name KEY_TAB

• 14 (0xe)

Key name KEY_GRAVE

• 15 (0xf)

Key name KEY_KPEQUAL

• 17 (0x11)

Key name KEY_LEFTALT

• 18 (0x12)

Key name KEY_LEFTSHIFT

• 19 (0x13)

Key name KEY_KATAKANAHIRAGANA

• 20 (0x14)

Key name KEY_LEFTCTRL

• 21 (0x15)

Key name KEY_Q

• 22 (0x16)

Key name KEY_1

• 26 (0x1a)

Key name KEY_Z

• 27 (0x1b)

Key name KEY_S

• 28 (0x1c)

Key name KEY_A

• 29 (0x1d)

Key name KEY_W

• 30 (0x1e)

Key name KEY_2

• 33 (0x21)

Key name KEY_C

• 34 (0x22)

Key name KEY_X

• 35 (0x23)

Key name KEY_D

• 36 (0x24)

Key name KEY_E

• 37 (0x25)

Key name KEY_4

• 38 (0x26)

Key name KEY_3

• 39 (0x27)

Key name KEY_KPJPCOMMA

• 41 (0x29)

Key name KEY_SPACE

• 42 (0x2a)

Key name KEY_V

• 43 (0x2b)

Key name KEY_F

• 44 (0x2c)

Key name KEY_T

• 45 (0x2d)

Key name KEY_R

• 46 (0x2e)

Key name KEY_5

• 47 (0x2f)

Key name KEY_F13

• 49 (0x31)

Key name KEY_N

• 50 (0x32)

Key name KEY_B

• 51 (0x33)

Key name KEY_H

• 52 (0x34)

Key name KEY_G

• 53 (0x35)

Key name KEY_Y

• 54 (0x36)

Key name KEY_6

• 55 (0x37)

Key name KEY_F14

• 58 (0x3a)

Key name KEY_M

• 59 (0x3b)

Key name KEY_J

• 60 (0x3c)

Key name KEY_U

• 61 (0x3d)

Key name KEY_7

• 62 (0x3e)

Key name KEY_8

• 63 (0x3f)

Key name KEY_F15

• 65 (0x41)

Key name KEY_COMMA

• 66 (0x42)

Key name KEY_K

• 67 (0x43)

Key name KEY_I

• 68 (0x44)

Key name KEY_O

• 69 (0x45)

Key name KEY_0

• 70 (0x46)

Key name KEY_9

• 73 (0x49)

Key name KEY_DOT

• 74 (0x4a)

Key name KEY_SLASH

• 75 (0x4b)

Key name KEY_L

• 76 (0x4c)

Key name KEY_SEMICOLON

• 77 (0x4d)

Key name KEY_P

• 78 (0x4e)

Key name KEY_MINUS

• 81 (0x51)

Key name KEY_RO

• 82 (0x52)

Key name KEY_APOSTROPHE

• 84 (0x54)

Key name KEY_LEFTBRACE

• 85 (0x55)

Key name KEY_EQUAL

• 88 (0x58)

Key name KEY_CAPSLOCK

• 89 (0x59)

Key name KEY_RIGHTSHIFT

• 90 (0x5a)

Key name KEY_ENTER

• 91 (0x5b)

Key name KEY_RIGHTBRACE

• 93 (0x5d)

Key name KEY_BACKSLASH

• 95 (0x5f)

Key name KEY_ZENKAKUHANKAKU

• 97 (0x61)

Key name KEY_102ND

• 98 (0x62)

Key name KEY_HIRAGANA

• 99 (0x63)

Key name KEY_KATAKANA

• 100 (0x64)

Key name KEY_HENKAN

• 102 (0x66)

Key name KEY_BACKSPACE

• 103 (0x67)

Key name KEY_MUHENKAN

• 105 (0x69)

Key name KEY_KP1

• 106 (0x6a)

Key name KEY_YEN

• 107 (0x6b)

Key name KEY_KP4

• 108 (0x6c)

Key name KEY_KP7

• 109 (0x6d)

Key name KEY_KPCOMMA

• 112 (0x70)

Key name KEY_KP0

• 113 (0x71)

Key name KEY_KPDOT

• 114 (0x72)

Key name KEY_KP2

• 115 (0x73)

Key name KEY_KP5

• 116 (0x74)

Key name KEY_KP6

• 117 (0x75)

Key name KEY_KP8

• 118 (0x76)

Key name KEY_ESC

• 119 (0x77)

Key name KEY_NUMLOCK

• 120 (0x78)

Key name KEY_F11

• 121 (0x79)

Key name KEY_KPPLUS

• 122 (0x7a)

Key name KEY_KP3

• 123 (0x7b)

Key name KEY_KPMINUS

• 124 (0x7c)

Key name KEY_KPASTERISK

• 125 (0x7d)

Key name KEY_KP9

• 126 (0x7e)

Key name KEY_SCROLLLOCK

• 127 (0x7f)

Key name KEY_SYSRQ

• 131 (0x83)

Key name KEY_F7

• 57360 (0xe010)

Key name KEY_SEARCH

• 57361 (0xe011)

Key name KEY_RIGHTALT

• 57362 (0xe012)

Key name unnamed

• 57364 (0xe014)

Key name KEY_RIGHTCTRL

• 57365 (0xe015)

Key name KEY_PREVIOUSSONG

• 57368 (0xe018)

Key name KEY_BOOKMARKS

• 57375 (0xe01f)

Key name KEY_LEFTMETA

• 57376 (0xe020)

Key name KEY_REFRESH

• 57377 (0xe021)

Key name KEY_VOLUMEDOWN

• 57379 (0xe023)

Key name KEY_MUTE

• 57383 (0xe027)

Key name KEY_RIGHTMETA

• 57384 (0xe028)

Key name KEY_STOP

• 57387 (0xe02b)

Key name KEY_CALC

• 57391 (0xe02f)

Key name KEY_COMPOSE

• 57392 (0xe030)

Key name KEY_FORWARD

• 57394 (0xe032)

Key name KEY_VOLUMEUP

• 57396 (0xe034)

Key name KEY_PLAYPAUSE

• 57399 (0xe037)

Key name KEY_POWER

• 57400 (0xe038)

Key name KEY_BACK

• 57402 (0xe03a)

Key name KEY_HOMEPAGE

• 57403 (0xe03b)

Key name KEY_STOPCD

• 57407 (0xe03f)

Key name KEY_SLEEP

• 57408 (0xe040)

Key name KEY_COMPUTER

• 57416 (0xe048)

Key name KEY_MAIL

• 57418 (0xe04a)

Key name KEY_KPSLASH

• 57421 (0xe04d)

Key name KEY_NEXTSONG

• 57424 (0xe050)

Key name KEY_MEDIA

• 57434 (0xe05a)

Key name KEY_KPENTER

• 57438 (0xe05e)

Key name KEY_WAKEUP

• 57449 (0xe069)

Key name KEY_END

• 57451 (0xe06b)

Key name KEY_LEFT

• 57452 (0xe06c)

Key name KEY_HOME

• 57455 (0xe06f)

Key name KEY_MACRO

• 57456 (0xe070)

Key name KEY_INSERT

• 57457 (0xe071)

Key name KEY_DELETE

• 57458 (0xe072)

Key name KEY_DOWN

• 57460 (0xe074)

Key name KEY_RIGHT

• 57461 (0xe075)

Key name KEY_UP

• 57463 (0xe077)

Key name KEY_PAUSE

• 57465 (0xe079)

Key name KEY_KPPLUSMINUS

• 57466 (0xe07a)

Key name KEY_PAGEDOWN

• 57469 (0xe07d)

Key name KEY_PAGEUP