NAME

spd-say – send text-to-speech output request to speech-dispatcher

SYNOPSIS

spd-say [*options*] *"some text"*

DESCRIPTION

send text−to−speech output request to speech−dispatcher

OPTIONS

−r, **−−rate**

Set the rate of the speech (between **−100** and +100, default: 0)

−p, **−−pitch**

Set the pitch of the speech (between **−100** and +100, default: 0)

−R, **−−pitch−range**

Set the pitch range of the speech (between **−100** and +100, default: 0)

−i, **−−volume**

Set the volume (intensity) of the speech (between **−100** and +100, default: 0)

−o, **−−output−module**

Set the output module

−O, **−−list−output−modules**

Get the list of output modules

−I, **−−sound−icon**

Play the sound icon

−l, **−−language**

Set the language (ISO code)

−t, **−−voice−type**

Set the preferred voice type (male1, male2, male3, female1, female2 female3, child_male, child_female)

−L, **−−list−synthesis−voices**

Get the list of synthesis voices

−y, **−−synthesis−voice**

Set the synthesis voice

−c, **−−character**

Speak the character

−k, **−−key**

Speak the key

−m, **−−punctuation−mode**

Set the punctuation mode (none, some, most, all)

−s, **−−spelling**

Spell the message

−x, **−−ssml**

Set SSML mode on (default: off)

−e, **−−pipe−mode**

Pipe from stdin to stdout plus Speech Dispatcher

−P, **−−priority**

Set priority of the message (important, message, text, notification, progress;default: text)

−N, **−−application−name**
> Set the application name used to establish the connection to specified string value (default: spd−say)

−n, **−−connection−name**
> Set the connection name used to establish the connection to specified string value (default: main)

−w, **−−wait**
> Wait till the message is spoken or discarded

−S, **−−stop**
> Stop speaking the message being spoken

−C, **−−cancel**
> Cancel all messages

−v, **−−version**
> Print version and copyright info

−h, **−−help**
> Print this info

Please report bugs to speechd−discuss@nongnu.org

COPYRIGHT

Copyright © 2002−2012 Brailcom, o.p.s.

This is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2, or (at your option) any later version. Please see COPYING for more details.

SEE ALSO

The full documentation for **spd-say** is maintained as a Texinfo manual. If the **info** and **spd-say** programs are properly installed at your site, the command

> **info spd-say**

should give you access to the complete manual.