# Assignment 2 — Machine Languages Due: Monday, April 18<sup>th</sup>

The LC-3 is an intentionally minimalistic computer architecture featuring simplified versions of the major hardware and software components of "real" modern computers. Nevertheless, in theory, all computable functions can be expressed in the machine language of the LC-3.

#### **Deliverables:**


GitHub Classroom: https://classroom.github.com/a/YD1hp6or

Required Files: lrotate.bin, rrotate.bin

Optional Files: none

#### Part 1: The LC-3 Simulator

Begin by installing LC3Tools 1.0.6: https://github.com/chiragsakhuja/lc3tools/releases/tag/v1.0.6. This program is available for all major operating systems; it is shown below as it appears on macOS, having loaded and converted the given sample.bin:




This initial view is the editor, which allows you to load, edit, and save machine code.

- The  $\Box$  button loads a machine code program from a file.
- The **b**utton saves the current program.

Recall that true machine code is encoded by the bits '0' and '1'; it is not written using the characters '0' and '1'. It also can't contain any extra whitespace or comments for readability. The editor thus also includes a button to convert textual "machine code", as shown above, into the appropriate actual binary data.

- $\cdot$  The  $\stackrel{\bullet}{\searrow}$  button converts the current program into binary and loads it into the simulator.
- The button switches over to the simulator.

Once a machine code program has successfully been converted into binary, switching to the *simulator* view shows the program loaded into memory and the PC set accordingly:



Additionally, the simulator displays the entire state of the LC-3:

- Each register is shown along with its value, displayed in both hexadecimal and decimal. Clicking on any register value edits it manually.
- Each memory location is shown with both its address and its value, displayed in both hexadecimal and decimal. Additionally, the simulator realizes that some of the data in memory originated as binary instructions, and displays those instructions. Clicking on any memory value edits it manually.
- . The  $\leftarrow$  and  $\rightarrow$  buttons scroll through memory.
- The small button next to each memory location sets the PC to its address.

At this point, the machine code program is ready to be run:

- The button begins execution from the current PC.
- The <> button switches back to the editor.

Complete documentation of the LC3Tools editor and simulator can be found here: https://github.com/chiragsakhuja/lc3tools/blob/master/docs/GuideToUsingLC3Tools.pdf.

## Part 2: The LC-3 ISA

In order to write your own machine code programs for the LC-3, you will likely refer often to the documentation of its valid machine instructions. Their formats and descriptions can be found in the LC-3's ISA, which has been rehosted here: http://users.csc.calpoly.edu/~cesiu/csc225/slides/lc3isa.pdf.

Instructions following these formats can be written and converted by the LC3Tools editor, then loaded and run in the LC3Tools simulator, according to the same procedure described above.

A significant amount of the work you will do in this course will involve writing, running, and debugging LC-3 programs in this environment. If you have any questions about any of the steps described so far, please do not hesitate to ask.

# Part 3: Rotating Bits

Recall that a bitwise *shift* moves every bit of a binary value to the left or to the right. In a left shift, this means that the most significant bit is discarded, whereas in a right shift, the least significant bit is discarded. In a bitwise *rotation*, the bit that would have been discarded is instead placed at the other end.

Complete the machine code program in lrotate.bin:

- · Your program's machine code must begin at memory location 0x3000.
- After running your program to completion, memory location 0x3051 must contain the value from memory location 0x3050, rotated once to the left. Memory location 0x3050 must be unchanged.
- It must be possible to rerun your program by manually resetting the PC to 0x3000. It should not require that the LC-3 be reinitialized or that any files be reloaded.

For example, suppose that, prior to running your program, memory location 0x3050 contains the value:

Then, after running your program to completion, memory location 0x3051 should contain the value:

Think carefully about which instructions you will use to accomplish this task<sup>1</sup>. While such is not a requirement of this assignment, a clear, concise program should be able to do this using fewer than 10 instructions (including the final HALT). Likewise, complete the machine code program in rrotate.bin:

- · Your program's machine code must begin at memory location 0x3000.
- After running your program to completion, memory location 0x3051 must contain the value from memory location 0x3050, rotated once to the right. Memory location 0x3050 must be unchanged.
- It must be possible to rerun your program by manually resetting the PC to 0x3000. It should not require that the LC-3 be reinitialized or that any files be reloaded.

For example, suppose that, prior to running your program, memory location 0x3050 contains the value:

Then, after running your program to completion, memory location 0x3051 should contain the value:

A clear, concise program should be able to do this using approximately 15 instructions.

### Part 4: Submission

The following files are required and must be pushed to your GitHub Classroom repository by the deadline:

- · lrotate.bin A working machine code program for left-rotating binary values, as specified.
- · rrotate.bin A working machine code program for right-rotating binary values, as specified.

The following files are optional:

 $\cdot$  none

Any files other than these will be ignored.

<sup>&</sup>lt;sup>1</sup>The runtime of a program is directly proportional to the number of instructions that must be executed.