

User Manual


Design millimeter-accurate labels with text, shapes, images, and QR codes, then export PDF or print — including sequential auto-counter runs.

Contents

- | | |
|-------------------------|---------------------------|
| 1. Workspace overview | 6. Grid & margins |
| 2. Getting started | 7. Templates |
| 3. Label size & presets | 8. Object library |
| 4. Adding objects | 9. Auto counter |
| 5. Editing & properties | 10. PDF, print & settings |
| | 11. Keyboard shortcuts |

1. Workspace overview

The Label Printer workspace has four areas: the header (size, templates, export), the left sidebar (add objects + layer list), the center canvas (your label), and the right inspector (grid, margins, properties).



Main workspace: tools on the left, label canvas in the center, properties on the right. Use **PDF** or **Print** in the top-right when you are ready to output.


2. Getting started

- 1 Open the app in a browser (`npm run dev`) or the desktop build.
- 2 Choose a label size from the size button in the header (for example **89 × 36 mm**).
- 3 Add objects from the left **Add Objects** panel — text, shapes, QR, image, or auto counter.
- 4 Select an object on the canvas or in the Objects list, then edit it in **Properties**.
- 5 Click **PDF** to download, or **Print** to open the system print dialog.

Tip: All positions and sizes use millimeters so printed output matches your physical label stock.

3. Label size & presets

Click the size button (for example **89 × 36 mm**) to pick a saved preset or open the preset manager to create custom widths and heights.



Label size menu: switch between presets (such as 80×30) or manage your own sizes.

- Changing size keeps your objects and clamps them so they stay inside the label.
- Use **Manage label size presets** to add, rename, or edit preset dimensions.

4. Adding objects


Use the **Add Objects** tools on the left:

TOOL	WHAT IT ADDS
Text (ABCD)	Editable text block with font, size, color, and alignment
Auto Counter (001-07x)	Numbered text that prints once per value in a range or count
Square / Circle / Line	Shapes with stroke, fill, and line styles
QR Code	QR matrix driven by the text/URL in Properties
Image	Upload an image file onto the label
Library	Reuse objects you previously saved

The **Objects** list below the tools shows every item on the label. Click a row to select it. Use ↑ / ↓ to change layer order, the lock icon to prevent moves/resizes, and × to delete.

5. Editing & properties

Select an object on the canvas (drag to move, use the handle to resize) or pick it from the Objects list. The right-hand **Properties** panel updates for that object.



Text properties: position/size in mm, text content, font family, bold/italic/underline, font size, letter spacing, color, and alignment.

Common controls

- **X / Y / W / H (mm)** — exact placement and size
- **Send Back / Bring Front** — layer order
- Locked objects ignore position and size changes until unlocked

QR codes

Edit **QR code info** (URL or text) and choose an error-correction level. The canvas QR updates as you type.

Images

After uploading, you can resize and position the image. When available, use **Make black** to convert the image for monochrome printing.


6. Grid & margins

On the right sidebar:

- **Show grid** — display a millimeter grid on the canvas
- **Snap to grid** — snap moves and resizes to the grid step
- **Grid mm** — grid spacing (1–20 mm)
- **Margins** — left/right/top/bottom safe areas in mm (shown as guides)

7. Templates

Open **Template** in the header to save, load, delete, import, or export designs.




Templates & Export: choose a saved template, Save the current design, Delete, Import JSON..., or download the current label as JSON.

- 1 Click **Save** and enter a name when prompted to store the design in the browser.
- 2 Pick a name from the list and click **Add** to load it onto the canvas.
- 3 Use **JSON** to download a file you can share or back up; use **Import JSON...** to restore one.

8. Object library


Save reusable objects (logos, standard QR layouts, repeated text styles) into the Object Library.



Object Library: select a saved object to place it on the label, or **Save selected object** to store the current selection.

9. Auto counter

Auto Counter creates numbered labels in one print run — useful for serials, lot numbers, or seat tags.




Auto Counter properties: set Start number, optional End number, or Count, then click **Print Auto Counter**.

- 1 Click the Auto Counter tool (or mark a text object as a counter).
- 2 Set **Start number**. Either set an **End number**, or leave End empty and set **Count**.
- 3 Style the counter text like any other text object.
- 4 Click **Print Auto Counter** to generate one page (label) per number.

Note: Leading zeros in Start/End are preserved in the printed sequence (for example start 001 → 001, 002, ...).

10. PDF, print & settings

- **PDF** — downloads a PDF of the current label
- **Print** — opens print preview / system print for the current label
- **Settings** (gear) — document theme and background color



Settings: pick a document theme (White, Sepia, Light blue, Light yellow, Black, Blueprint) or set a custom background color. Themes also update line/text colors for contrast.

11. Keyboard shortcuts

SHORTCUT	ACTION
Ctrl + Z	Undo
Ctrl + Y or Ctrl + Shift + Z	Redo
Ctrl + C	Copy selected object
Ctrl + V	Paste copied object
Delete / Backspace	Delete selected object (when focus is not in a form field)

On macOS, use

Cmd

 instead of

Ctrl

.

Label Printer user manual — generated from the live app with real screenshots.

Web version: docs/user-manual.html · PDF version: docs/user-manual.pdf