

Bug Report — Web App (DEF)

Bug Report — Web App (DEF)

Project: **Web App** · Key: **DEF** · Date: August 18, 2026

Summary Table

ID	Summary	Priority	Status	Creation Date
DEF-1	The Clear button does not clear the email input field	 Low	To be completed	August 18, 2026
DEF-2	The "Каталог" drop-down opens the category in a new tab	 Medium	To be implemented	August 18, 2026
DEF-3	Product option selectors do not update the price without a full page reload	 High	To be implemented	August 18, 2026
DEF-4	Minimum order / free shipping information not displayed in the cart or address step	 Medium	To be implemented	August 18, 2026
DEF-5	"Отметить все как прочитанное" does not clear the unread indicator immediately	 Low	To be implemented	August 18, 2026

 **DEF-3 · High Priority**

Product option selectors (size/color) do not update the price and availability without a full page reload—a direct violation of the stated requirement.

Assigned to: Artyom · **Created:** August 18, 2026 · **Status:** To Be Completed

Steps to Reproduce

1. Open the Ozon homepage (or product catalog)
2. Go to a product page with color or size options
3. Wait for the page to fully load
4. Open DevTools → Network tab, set the filter to " `Doc`"
5. Click on a different color/size
6. Note the appearance of a new request with Type = document and status 200 OK

Expected result

- A request of type `fetch` or `xhr` appears in the Network tab
- The `document` type is missing—the page does **not reload**

Actual result

- A new request with the `"document"` type appears; the old document is replaced by the new one—confirming **a full page reload** instead of a dynamic update of elements

Name ▼	Status	Type	Initiator	Size	Time
 longsliv-ba...	200	document		115 kB	142 ms

DEF-2 · Medium Priority

In the “Каталог” drop-down menu, it is not possible to open each category directly in the main window.

| **Assigned to:** Artyom · **Created:** August 18, 2026 · **Status:** To Be Completed

Reproduction Steps

1. Click the "Каталог" button on the home page
2. Click any category from the list

Expected Result

- The category page opens **in the main tab**

Actual Result

- **A new tab** opens with the category page
-

DEF-4 · Medium Priority

Information regarding the minimum order amount or free shipping is not displayed during the early stages (in the cart or when selecting an address).

| **Assigned to:** Artyom · **Created:** August 18, 2026 · **Status:** To Be Completed

Prerequisites

- The user must be logged in

Reproduction Steps

1. Select any product and add it to the cart
2. Select a delivery address that is not valid
3. Check for a warning on the "Корзина" tab

Expected result

- The "Корзина" page displays a warning that the order cannot be placed

Actual result

- **No warnings appear** on the "Корзина" page
-

● DEF-1 · Low Priority

The "Очистить" button does not clear the email input field.

| **Assigned to:** Artyom · **Created:** August 18, 2026 · **Status:** To Be Completed

Steps to reproduce


1. Open the login page
2. Click the "Войти по почте" button
3. Enter a few characters in the email field
4. Click the clear button (x)


Expected Result

- The input field **is cleared**

Actual result

- The input field **is not cleared**, and the clear button disappears





● DEF-5 · Low Priority

The "Отметить все как прочитанное" button does not remove the unread message indicator without restarting the app or reloading the page.

| Assigned to: Artyom · Created: August 18, 2026 · Status: To Be Completed

Prerequisites

- The user must be logged in

Reproduction Steps

1. Go to your profile → "Сообщения" tab
2. Click the "Отметить все как прочитанное" button

Expected Result

- The notification indicator **disappears** from all icons without restarting

Actual Result

- The notification indicator **does not disappear** without restarting the app