

Disk Volumes

Disk Volumes gives you complete control over the persistent storage attached to your virtual machines. List volumes from any cloud account, then create, modify, encrypt, attach, detach, snapshot, or delete them — all without leaving QuickInfra.

What is Disk Volumes?

Disk Volumes is the storage management layer of QuickInfra. It surfaces all EBS volumes across your cloud accounts in a unified list, and gives you a rich set of actions to manage their full lifecycle — from initial creation through encryption, resizing, attachment to instances, snapshotting for backup, and eventual deletion.

Whether you need to provision fresh storage for a new server, resize an existing volume as your data grows, or take a point-in-time snapshot before a risky deployment, Disk Volumes handles it all through a single action interface. Select an action, configure the parameters, and execute — QuickInfra handles the API calls to your cloud provider.

Note: Volume data is fetched live from your cloud provider. The list always reflects the real-time state of your storage across all selected accounts and regions.

Multi-Attach Enabled ☐ Is Encrypted ☐

KMS Key

Volume Tags

Attachment Details

--Select Action--

- Create New
- Modify
- Delete

Attach

Detach

Snapshot

--Select Action--

MFA (Optional) Execute

The Disk Volumes action panel — select an operation such as Create, Modify, Attach, Detach, Snapshot, or Delete and configure it for your volume.

How to Manage Your Volumes

1 **Navigate to Manage → Disk Volumes**

From the left sidebar select **Manage** then **Disk Volumes**. Use the filter controls to select your **Cloud Provider**, **Cloud Account**, and **Region**, then fetch your volumes.

2 **Select a volume**

Your volumes appear in the list with their name, ID, size, type, state, and any attached instance. Click the volume you want to work with to bring up the action panel.

3 **Choose an action**

From the **Select Action** dropdown in the Attachment Details panel, choose the operation you want to perform. The available actions are described in the section below. Configure any required parameters — such as size, encryption settings, KMS key, or tags — then click **Execute**.

Available Actions

Create New — Provision a brand new EBS volume. Specify the size, volume type, availability zone, and whether it should be encrypted. You can also enable **Multi-Attach** for volumes that need to be shared across multiple instances simultaneously.

Modify — Resize an existing volume or change its type without detaching it from the instance. Useful for scaling storage live as your application grows.

Delete — Permanently remove the volume from your cloud account. The volume must be detached before deletion.

Attach — Connect an existing volume to a running or stopped instance. Specify the target instance and the device path for the attachment.

Detach — Safely disconnect a volume from its current instance without destroying the data. The volume becomes available for reattachment elsewhere.

Snapshot — Create a point-in-time backup of the volume. Snapshots are stored in your cloud account and can be used to restore data or create new volumes from a known good state.

Encryption

When creating a new volume, you can enable encryption by checking **Is Encrypted**. Provide a **KMS Key** ARN if your organisation manages its own encryption keys — leave it blank to use the default AWS-managed key. Encrypted volumes protect data at rest and in transit between the volume and the instance.



Tip: Use **Volume Tags** to label your volumes with key-value pairs such as *Name=quickinfra-app-root-ebs* or *env=prod*. Tags make it significantly easier to identify volumes, track costs by environment, and apply access policies.



Warning: Deleting a volume is permanent and irreversible. Always take a **Snapshot** before deleting any volume that contains data you may need to recover later.

Key Things to Know

A volume must be in the same availability zone as the instance you want to attach it to.

Modifying a volume (resize or type change) takes effect immediately but may require a file system extension inside the OS to use the new space.

Snapshots are incremental — only changed blocks are stored after the first snapshot, keeping backup costs low.

Multi-Attach is supported only for io1 and io2 volume types and requires a cluster-aware file system on the attached instances.

Volumes set to **Delete on Termination** will be automatically removed when the attached instance is terminated — ensure this is intentional before enabling it.