


DTP LAB Time:



Both Switches Dynamic Desirable	
S1(config)#interface e0/0	
S1(config-if)#switchport mode dynamic desirable	
S1#show interfaces trunk	
S2(config)#interface e0/0	
S2(config-if)#switchport mode dynamic desirable	
S2#show interfaces trunk	

s1#show interfaces trunk

Port	Mode	Encapsulation	Status	Native vlan
Et0/0	desirable	n-isl	trunking	1

s2#show interfaces trunk

Port	Mode	Encapsulation	Status	Native vlan
Et0/0	desirable	n-isl	trunking	1

Both Switches Dynamic Auto
S3(config)#interface e0/0 S3(config-if)#switchport mode dynamic auto
S3#show interfaces trunk S3#show interfaces e0/0 switchport
S4(config)#interface e0/0 S4(config-if)#switchport mode dynamic auto
S4#show interfaces trunk S4#show interfaces e0/0 switchport

```

S3#show interfaces e0/0 switchport
Name: Et0/0
Switchport: Enabled
Administrative Mode: dynamic auto
Operational Mode: static access
Administrative Trunking Encapsulation: negotiate
Operational Trunking Encapsulation: native
Negotiation of Trunking: On
S4#show interfaces e0/0 switchport
Name: Et0/0
Switchport: Enabled
Administrative Mode: dynamic auto
Operational Mode: static access
Administrative Trunking Encapsulation: negotiate

```

S5 Dynamic Desirable & S6 Dynamic Auto
S5(config)#interface e0/0 S5(config-if)#switchport mode dynamic desirable
S5#show interfaces trunk S5#show interfaces e0/0 switchport
S6(config)#interface e0/0 S6(config-if)#switchport mode dynamic auto
S6#show interfaces trunk S6#show interfaces e0/0 switchport

```
S5#show interfaces trunk
```

Port	Mode	Encapsulation	Status	Native vlan
Et0/0	desirable	n-isl	trunking	1

```
S6#show interfaces trunk
```

Port	Mode	Encapsulation	Status	Native vlan
Et0/0	auto	n-isl	trunking	1

S7 Dynamic Desirable & S8 Trunk				
S7(config)#interface e0/0				
S7(config-if)#switchport mode dynamic desirable				
S7#show interfaces trunk				
S7#show interfaces e0/0 switchport				
S8(config)#interface e0/0				
S8(config-if)#switchport trunk encapsulation dot1q				
S8(config-if)#switchport mode trunk				
S8#show interfaces trunk				
S8#show interfaces e0/0 switchport				

s7#show interfaces trunk

Port	Mode	Encapsulation	Status	Native vlan
Et0/0	desirable	n-802.1q	trunking	1

s8#show interfaces trunk

Port	Mode	Encapsulation	Status	Native vlan
Et0/0	on	802.1q	trunking	1

S9 Dynamic Auto & S10 Trunk				
S9(config)#interface e0/0				
S9(config-if)#switchport mode dynamic auto				
S9#show interfaces trunk				
S9#show interfaces e0/0 switchport				
S10(config)#interface e0/0				
S10(config-if)#switchport trunk encapsulation dot1q				
S10(config-if)#switchport mode trunk				
S10#show interfaces trunk				
S10#show interfaces e0/0 switchport				

s9#show interfaces trunk

Port	Mode	Encapsulation	Status	Native vlan
Et0/0	auto	n-802.1q	trunking	1

s10#show interfaces trunk

Port	Mode	Encapsulation	Status	Native vlan
Et0/0	on	802.1q	trunking	1