



PC0
Physical
Config
Desktop
Custom Interface
Command Prompt
X
Packet Tracer PC Command Line 1.0
PC>ping 192.168.1.1
Pinging 192.168.1.1 with 32 bytes of data:
Reply from 192.168.1.1: bytes=32 time=1ms TTL=255
Reply from 192.168.1.1: bytes=32 time=0ms TTL=255
Reply from 192.168.1.1: bytes=32 time=0ms TTL=255
Reply from 192.168.1.1: bytes=32 time=0ms TTL=255
Ping statistics for 192.168.1.1:
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
Minimum = 0ms, Maximum = 1ms, Average = 0ms
PC>ping 203.0.113.10
Pinging 203.0.113.10 with 32 bytes of data:
Request timed out.
Reply from 203.0.113.10: bytes=32 time=0ms TTL=127
Reply from 203.0.113.10: bytes=32 time=0ms TTL=127
Reply from 203.0.113.10: bytes=32 time=0ms TTL=127
Ping statistics for 203.0.113.10:
Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
Approximate round trip times in milli-seconds:
Minimum = 0ms, Maximum = 0ms, Average = 0ms




```
Router(config)#interface gigabitEthernet 0/1
Router(config-if)#ip address 203.0.113.1 255.255.255.0
Router(config-if)#ip nat outside
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state
to up
exit
```





```
Router>
Router>enable
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#interface gigabitEthernet 0/0
Router(config-if)#ip address 192.168.1.1 255.255.255.0
Router(config-if)#ip nat inside
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state
to up
exit
```



```
Router(config)#access-list 1 permit 192.168.1.0 0.0.0.255
Router(config)#ip nat inside source list 1 interface gigabitEthernet 0/1 overload
Router(config)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console
show ip interface brief
Interface              IP-Address      OK? Method Status                Protocol

GigabitEthernet0/0     192.168.1.1     YES manual up                    up

GigabitEthernet0/1     203.0.113.1     YES manual up                    up

Vlan1                  unassigned      YES unset  administratively down down
Router#show ip nat translations
Pro  Inside global     Inside local       Outside local      Outside global
icmp 203.0.113.1:5     192.168.1.10:5     203.0.113.10:5     203.0.113.10:5
icmp 203.0.113.1:6     192.168.1.10:6     203.0.113.10:6     203.0.113.10:6
icmp 203.0.113.1:7     192.168.1.10:7     203.0.113.10:7     203.0.113.10:7
icmp 203.0.113.1:8     192.168.1.10:8     203.0.113.10:8     203.0.113.10:8

Router#show ip nat statistics
Total translations: 0 (0 static, 0 dynamic, 0 extended)
Outside Interfaces: GigabitEthernet0/1
Inside Interfaces: GigabitEthernet0/0
Hits: 3  Misses: 4
Expired translations: 4
Dynamic mappings:
Router#
```