

```

CREATE TABLE BANK_29(
    BANKCODE VARCHAR(3) PRIMARY KEY,
    BANKNAME VARCHAR(50) NOT NULL,
    HEADOFFICE VARCHAR(50),
    BRANCHES INT CHECK(BRANCHES>0)
);
INSERT INTO BANK_29 VALUES('HDF','HDFC BANK','MUMBAI',6000);
INSERT INTO BANK_29 VALUES('SBI','STATE BANK OF INDIA','MUMBAI',22000);
INSERT INTO BANK_29 VALUES('PNB','PUNJAB NATIONAL BANK','PUNE',7000);
INSERT INTO BANK_29 VALUES('AXI','AXIS BANK','ERNAKULAM',5000);
INSERT INTO BANK_29 VALUES('CAN','CANARA BANK','KOTTAYAM',6500);
INSERT INTO BANK_29 VALUES('UNI','UNION BANK','DELHI',3000);
INSERT INTO BANK_29 VALUES('IDB','IDBI BANK','MUMBAI',2000);
SELECT * FROM BANK_29;

```

	BANKCODE	BANKNAME	HEADOFFICE	BRANCHES
1	HDF	HDFC BANK	MUMBAI	6000
2	SBI	STATE BANK OF INDIA	MUMBAI	22000
3	PNB	PUNJAB NATIONAL BANK	PUNE	7000
4	AXI	AXIS BANK	ERNAKULAM	5000
5	CAN	CANARA BANK	KOTTAYAM	6500
6	UNI	UNION BANK	DELHI	3000
7	IDB	IDBI BANK	MUMBAI	2000

```

CREATE TABLE BRANCH_29 (
    BRANCHID INT PRIMARY KEY,
    BRANCHNAME VARCHAR(50) DEFAULT 'New Delhi',
    BANKID VARCHAR(3),
    FOREIGN KEY (BANKID) REFERENCES BANK_29(BANKCODE)
);
INSERT INTO BRANCH_29 VALUES(101,'KOTTAYAM','HDF');
INSERT INTO BRANCH_29 VALUES(102,'ERNAKULAM','SBI');
INSERT INTO BRANCH_29 VALUES(103,'KOTTAYAM','PNB');
INSERT INTO BRANCH_29 VALUES(104,DEFAULT,'HDF');
INSERT INTO BRANCH_29 VALUES(105,'THRISSUR','SBI');
INSERT INTO BRANCH_29 VALUES(106,'KOTTAYAM','IDB');
SELECT * FROM BRANCH_29;

```

	BRANCHID	BRANCHNAME	BANKID
1	101	KOTTAYAM	HDF
2	102	ERNAKULAM	SBI
3	103	KOTTAYAM	PNB
4	104	New Delhi	HDF
5	105	THRISSUR	SBI
6	106	KOTTAYAM	IDB

1.

```

CREATE VIEW BANK_HEAD_OFFICE AS SELECT * FROM BANK_29 WHERE HEADOFFICE='ERNAKULAM';
SELECT * FROM BANK_HEAD_OFFICE;

```

	BANKCODE	BANKNAME	HEADOFFICE	BRANCHES
1	AXI	AXIS BANK	ERNAKULAM	5000

2.

```
CREATE VIEW BANK_BRANCH AS SELECT B.* FROM BANK_29 B JOIN BRANCH_29 BR ON
B.BANKCODE=BR.BANKID WHERE BR.BRANCHNAME='KOTTAYAM';
SELECT * FROM BANK_BRANCH;
```

	BANKCODE	BANKNAME	HEADOFFICE	BRANCHES
1	HDF	HDFC BANK	MUMBAI	6000
2	PNB	PUNJAB NATIONAL BANK	PUNE	7000
3	IDB	IDBI BANK	MUMBAI	2000

3.

```
CREATE VIEW BANKS_MORE_THAN_50 AS SELECT * FROM BANK_29 WHERE BRANCHES>50;
SELECT * FROM BANKS_MORE_THAN_50;
```

	BANKCODE	BANKNAME	HEADOFFICE	BRANCHES
1	HDF	HDFC BANK	MUMBAI	6000
2	SBI	STATE BANK OF INDIA	MUMBAI	22000
3	PNB	PUNJAB NATIONAL BANK	PUNE	7000
4	AXI	AXIS BANK	ERNAKULAM	5000
5	CAN	CANARA BANK	KOTTAYAM	6500
6	UNI	UNION BANK	DELHI	3000
7	IDB	IDBI BANK	MUMBAI	2000

4.

```
CREATE VIEW BANK_BRANCH_DETAILS AS SELECT B.BANKNAME, BR.BRANCHNAME FROM
BANK_29 B JOIN BRANCH_29 BR ON B.BANKCODE=BR.BANKID;
SELECT * FROM BANK_BRANCH_DETAILS;
```

	BANKNAME	BRANCHNAME
1	HDFC BANK	New Delhi
2	HDFC BANK	KOTTAYAM
3	STATE BANK OF INDIA	THRISSUR
4	STATE BANK OF INDIA	ERNAKULAM
5	PUNJAB NATIONAL BANK	KOTTAYAM
6	IDBI BANK	KOTTAYAM

5.

```
CREATE VIEW BANK_OUTSIDE_ERNAKULAM AS SELECT * FROM BANK_29
WHERE HEADOFFICE<>'ERNAKULAM';
SELECT * FROM BANK_OUTSIDE_ERNAKULAM;
```

12	BANKCODE	12	BANKNAME	12	HEADOFFICE	12	BRANCHES
1	HDF		HDFC BANK		MUMBAI		6000
2	SBI		STATE BANK OF INDIA		MUMBAI		22000
3	PNB		PUNJAB NATIONAL BANK		PUNE		7000
4	CAN		CANARA BANK		KOTTAYAM		6500
5	UNI		UNION BANK		DELHI		3000
6	IDB		IDBI BANK		MUMBAI		2000