

Module

FSMO – Flexible Single Master Operation


FSRM Roles

1. Schema Master
2. Domain Naming Master
3. PDC
4. RID Pool Master
5. Infrastructure Master


Forest level Roles

Domain level Roles

» The first DC of the domain has all five roles.



Forest: iforward.com
Schema and DNM






FSRM Roles

- ✓ All roles are flexible that means we can transfer the roles to other domain controller of same domain.

Schema Roles

- ✓ It is the forest Level role
- ✓ Schema master can change in schema partition
- ✓ Consist of **Objects types** and its **Attributes**
- ✓ By default, the **root** domain controller (First Domain) having this roles
- ✓ Other domain controller (child & Tree) of the forest are not able to change in schema.
- ✓ Means it cannot add new classes and attributes in schema.



Schema Roles


- ✓ Object types defined in schema master that why we are able to create a objects.

Object Types	Object
User	Tom, Bob, Jay
Group	IT Team, IT Manager
Computer	PC1, PC2
Printer	HP
OU	IT, HR, Finance

- ✓ For example, To see the attributes for particular object open dsa.msc > click on view and tick advance features > go to properties of object and open attributes editor tab

Schema Roles

- ✓ Attributes Types
- ✓ It is described the object.
- ✓ To see the schema partition run below command ((W+R))
- ✓ **regsvr32 schmmgmt.dll**
- ✓ Open MMC and add Active Directory Schema to the console
- ✓ We can create the new attributes from that domain which has schema master role






Schema Roles


- ✓ Transfer the role: **Schema Master**
- ✓ Transfer of the roles from root domain controller to additional domain controller, both domain must up and running state.
- ✓ Go to the **Active Directory Schema console**
- ✓ The one who needs a role need to go to that domain.
- ✓ Right click on operation master and change (Administrator)
- ✓ Verify using below command
- ✓ **netdom query fsmo**

Domain Naming Master (DNM)

- ✓ Whenever the new domain added or deleted from the forest a DNM is consulted.
- ✓ Checks and Maintains the Uniqueness of the Domain Names in the Whole Forest.
- ✓ It is Responsible for Adding, Removing and Renaming the domain names in the whole Forest.



Domain Naming Master (DNM)






Domain Naming Master (DNM)


- ✓ Transfer the role: **DN Master**
- ✓ Transfer of the roles from root domain controller to additional domain controller, both domain must up and running state.
- ✓ Go to server manager page (tools) >> **Active directory domain and trust**
- ✓ Run command: **domain.msc**
- ✓ The one who needs a role need to go to that domain.
- ✓ Right click on operation master and change
- ✓ Verify using below command
- ✓ **netdom query fsmo**

Active Directory Partition

✓ Total 5 partitions:

1. **Schema Partitions** →
regsvr32 schmmgmt.dll
2. **Configurations Partition** →
domain.msc
3. **Domain Partition** →
dsa.msc
4. **Application Partition** →
dnsmgmt.msc





All partitions together comprise the active directory database



Active Directory Partition

- ✓ **Schema Partitions**
- ✓ Consist the object types and there attributes
- ✓ All DC in the forest will have same schema partition
- ✓ **Schema master works on the schema partition**



Active Directory Partition

- ✓ **Configuration Partitions**
- ✓ Consist the network topology like domain and trust exists in a forest
- ✓ All DC in the forest will have same configuration partition
- ✓ **DN master works on the configuration partition**



Active Directory Partition

- ✓ **Domain Partitions**
- ✓ Consist of all the objects in active directory
- ✓ All DC in the domain will have same Domain Partition
- ✓ **RID/Infra/PDC master works on Domain Partition**



Active Directory Partition

- ✓ **Application Partitions**
- ✓ Created by application like DNS
- ✓ All DC in the domain will have same Application Partition