Command Line Interface

Zoho Vault's command line interface (CLI) acts as a standalone desktop client that allows users to add, edit, search, and modify passwords in their vault. Users can also generate strong new passwords using the built-in password generator. The CLI can be accessed from the terminal of your Linux, Windows, and Mac devices. Download the Zoho Vault CLI here.

Setting up your CLI

1. Add the package path to the environment variable to ensure it can work from any path.
2. Once set, you can log in into your Zoho account using the command **zv login**.
3. Access the URL displayed in the console from your browser to validate your authentication.
4. Access your Zoho Vault using **zv unlock [master-password]**.

Note: Learn how to [set your Vault CLI to path here](). Users on newer MacOS versions might see an error stating "*zv" was blocked from use because it is not from an identified developer*. To fix this, go to **Settings** > **Security & Privacy** > **General**. Select **Open Anyway** as shown in the screenshot, then try to run the package again. You will get the same error message again but it will include an **Open** option. Click **Open** to run the package normally.



Available commands

The following commands are currently supported in the Vault CLI. You can list all the available commands using **zv** or **zv -h** commands. To learn more about any particular command and its usage, use **zv <command> -h** or **zv <command> --help**. Use the following commands with **./** in front of them on Linux and Mac OS.

Command	Description
add	Add passwords to Zoho Vault
download	Download file attachments from your vault
generate-password	Generate new passwords
generate-template	Generate password templates
get	Find complete details about your password
get-default	Display default values of commands
list	List passwords and password categories
lock	End your current Zoho Vault session by clearing your master password
login	Log in to your Zoho account

logout	Log out of your Zoho account
search	Search for passwords in your vault
set-default	Set default values for commands
unlock	Access your Zoho Vault account
update	Edit and update password details

Commands with detailed actions

Let's take a deeper look into possible commands you can run based on the operation.

View Passwords

Command	**Description**
zv add	**Add new passwords**
zv generate-template	**Generate template to add passwords using a template**
zv add -f <file>	**Add passwords using the template file**

Search Passwords

Command	Description
zv search -k <search-term>	Search all your passwords
zv search -k <search-term> --name	Search matching terms by name
zv search -k <search-term> --tags	Search matching terms that have tags
zv search -k <search-term> --desc	Search matching terms by description

Update Passwords

Command	Description
zv update -id <password-id>	Update passwords using the password ID
zv search -k <password-name>	Find the password ID

Generate Strong Passwords

Command	Description
zv generate-password	Generate passwords
zv generate-password --use-password-policy	Generate passwords using the password policies
zv generate-password -len 10 -upper -lower -number -spl 3	Generate passwords using custom options in generator

Defaults in Zoho Vault CLI

Configure defaults for repetitive options specific to a command.

> **Note:** Use **--use-default** in commands to execute them with default options

Command	Description
zv set-default	Add a new default
zv set-default --command <commands>	Add a new default for a specific command
zv get-default	View all default values

Terminating your session

Command	Description
zv logout	**Log out from your session**