# **Module 1 Assignment Commands:**

#### **Bash Commands:**

## For listing active subscription:

az account list --output table az account list

#### For Creating a resource group:

az group create -n new-rg -l southcentralus az group create --name new-rg --location southcentralus

#### For creating 3 or more resource groups using single command:

az group create -n rg-11 -l westus && az group create -n rg-22 -l westus && az group create -n rg-33 -l westus

## For listing all the resource groups in a subscription:

az group list

## For listing all the resource groups in a subscription in tabular format:

az group list -o table az group list --output table

# For listing resource groups in a particular region:

az group list --query "[?location=='westus']"

## For listing resource groups in a particular region in tabluar format:

az group list --query "[?location=='westus']" -o table

# For deleting a resource group:

az group delete -n rg-1

# For deleting all the resource groups in a particular region:

az group list --query "[?location=='westus']".name -o tsv | xargs -otl az group delete -n

### **PowerShell Commands:**

## For listing all of the subscriptions:

Get-AzSubscription

## For creating a resource group:

New-azresourcegroup -n rg-powershell -l southcentralus New-azresourcegroup -name rg-powershell -location southcentralus

#### Creating 3 or more resource group using a single command:

New-azresourcegroup -n rg-1 -l westus && New-azresourcegroup -n rg-2 -l westus && New-azresourcegroup -n rg-3 -l westus

#### For listing all the resource groups in your subscription:

Get-azresourcegroup

# For listing resource groups in tabluar format:

Get-azresourcegroup | Format-Table

### For listing resource groups in a particular region:

Get-azresourcegroup -l westus

#### For listing resource groups in a particular region in tabluar format:

Get-azresourcegroup -l westus | Format-Table

## For Deleting a particular resource group:

Remove-azresourcegroup -n rg-2 Remove-azresourcegroup -name rg-2

# For deleting a resource group forcefully (It will not ask for the confirmation):

Remove-azresourcegroup -n rg-3 -Force

# For deleting all the resource groups in a particular region using single command:

Get-azresourcegroup -l westus | remove-azresourcegroup

Get-azresourcegroup -I westus | remove-azresourcegroup -Force //Will forcefully delete the resource groups without even asking for confirmation