

Claude Code on Amazon Bedrock

QUICK REFERENCE



ANTHROPIC

Project & memory

Project memory

```
/init · /memory
```

Append to memory

```
# <note>
```

Files into context

```
@path · @dir/ · @server:res
```

Run a shell command

```
! <command> # shell mode
```

Sessions & context

Continue / resume

```
claude -c · --resume [id]
```

Reset · summarize · inspect

```
/clear · /compact · /context
```

Fork / roll back

```
/branch · /fork · /rewind
```

Name / save

```
/rename · /export
```

Model & effort

Switch model

```
/model [name]
```

Reasoning effort

```
/effort low|medium|high|xhigh|max
```

Max-effort mode

```
/effort ultracode
```

Set any setting

```
/config key=value
```

Permissions & modes

Allow / ask / deny

```
/permissions
```

Plan before editing

```
/plan [task] # Shift+Tab twice
```

Auto mode (hands-off)

```
--permission-mode auto
```

Auto-accept edits

```
--permission-mode acceptEdits
```

Sandbox mode

```
/sandbox
```

Autonomy & workflows

Work until a condition

```
/goal <condition>
```

Repeat every interval

```
/loop 5m <prompt>
```

One task as a workflow

```
ultracode: <task>
```

Watch dynamic workflows

```
/workflows
```

Deep research (built-in)

```
/deep-research <question>
```

Spin up subagents

```
> use subagents for X, Y and Z
```

Extend Claude Code

Skills / subagents

```
/skills · /agents
```

Create a custom skill

```
.claude/skills/<name>/SKILL.md  
> scaffold a skill for <task>
```

Add plugin from git

```
/plugin marketplace add owner/repo
```

Install / list plugins

```
/plugin install name@mp · list
```

Add an MCP server

```
claude mcp add <name> -- <cmd>
```

List / manage MCP

```
/mcp · claude mcp list
```

Headless & automation

Headless / print mode

```
claude -p "<prompt>"
```

Structured JSON output

```
--output-format json|stream-json
```

Print a run's cost

```
claude -p "..." --output-format json  
| jq '.total_cost_usd'
```

Fan out across worktrees

```
/batch <instruction>
```

Amazon Bedrock config

Enable Bedrock

```
export CLAUDE_CODE_USE_BEDROCK=1
```

Setup wizard

```
/setup-bedrock
```

Pin the AWS Region

```
export AWS_REGION=us-east-1
```

Pin a model version

```
ANTHROPIC_DEFAULT_SONNET_MODEL=  
us.anthropic.claude-sonnet-4-6
```