CIS 375 CHAPTER 9

Wide Area Networks



Outline

- WAN Service Types
 - Dedicated-Circuit Networks
 - Packet-Switched Networks
 - Virtual Private Networks
- Best Practices WAN Design
- Implications for Management



Wide Area Networks

- Wide area networks (WANs) run long distances connecting different buildings or offices
 - Organizations typically do not own all of the land upon which the WAN circuits run
 - May span a city, regions, or even countries
- Often built using leased circuits from common carriers
 - e.g., AT&T, Sprint, Verizon, BT, Telefónica, Level 3, Tata
 Communications



Wide Area Networks

- Common services
 - Dedicated-circuit networks
 - Packet-switched networks
 - Virtual private networks (VPNs)




- Use full duplex circuits from common carriers called leased lines or private lines to create point-to-point links between organizational locations
- Carrier installs circuit that connects locations
- Connect LANs to leased lines using modem, multiplexer, or channel service unit / data service unit (CSU/DSU)
- Billed at a flat fee per month with unlimited use of the circuit
- Adding/removing lines or increasing/decreasing capacity may be difficult, time consuming, and expensive



Private line services

- 9.1 Basic Architecture
- □ Multiplexers, or
- □ CSU (Channel Service Unit) and/or DSU (Data Service Unit)
- □ Circuit is established between 2 communicating devices
- □ Ethernet frame / IP packet is translated to Layer 2 / Layer 3 protocol used by the WAN
- **Billing**: flat fee / month & unlimited use of the circuit
- ☐ Architecture: ring, star, or mesh





- Three architectures (physical topologies) for dedicated-circuit networks
 - 1. Ring
 - 2. Star
 - 3. Mesh



Ring Architecture

FIGURE 9-2 Ring-based design





Star Architecture


FIGURE 9-3 Star-based design







Mesh Architecture

FIGURE 9-4 Mesh design











Architecture	Advantages	Disadvantages
Ring	 Robust to loss of any one circuit 	 Long routes may increase communication latency
Star	 Simpler management Messages require 1 or 2 hops Circuit failure primarily affects a single site 	 Susceptible to traffic problems Failure of the central site will cause complete network failure
Mesh	Generally short routesRobust to the circuit loss or overloaded circuits	Expensive



- Two types of dedicated circuit services:
 - 1. T-carrier network
 - 2. Synchronous optical network (SONET)



- T-carrier services
 - Most common dedicated circuit used in North America using copper wires
 - Similar to E-carrier services in Europe

T-carrier Designation	Digital Signal Designation	Speed
Fractional T1*	DS0	64 Kbps
T1*	DS1	1.544 Mbps
T2	DS2	6.312 Mbps
T3*	DS3	44.736 Mbps
T4	DS4	274.176 Mbps





- Synchronous optical network (SONET)
 - ANSI standard for optical fiber transmission
 - Similar to synchronous digital hierarchy (SDH) used outside of North America

SONET Designation	SDH Designation	Speed
OC-1	STM-0	51.84 Mbps
OC-3	STM-1	155.52 Mbps
OC-12	STM-4	622.08 Mbps
OC-48	STM-16	2.488 Gbps
OC-192	STM-64	9.953 Gbps



- Operate more like LANs and BNs than dedicatedcircuit networks
- Connect to carrier network using packet assembler/disassember (PAD)
 - Translates messages between protocols
 - e.g. Frame Relay Assembler/Disassembler
- Customers pay a fixed price for a connection to the carrier and then a fee for the data transmitted



- Packets from separate messages may be interleaved to maximize efficiency
- Permanent Virtual Circuits (PVCs) are connections between different locations in the packet network
 - Make packet-switched networks act like dedicated circuit networks
- Switched Virtual Circuits (SVCs) change dynamically




Data rates

- Different locations may have different transmission speeds to the carrier network
- Customers specify the rates per PVC
- The committed information rate (CIR) is guaranteed by the service provider
- Packets exceeding the CIR up to the maximum allowable rate (MAR) may be discarded if the network becomes overloaded



- More like Ethernet and IP networks used in LAN & BN
- Multiple connections exist simultaneously between devices
- □ PAD (packet assembly/disassembly device)
- Ethernet frame / IP packet is translated to Layer 2 / Layer 3 protocol used by the WAN
- □ Different locations can have different connection speeds into the cloud
 - □ **PVCs** (permanent virtual circuit)
 - □ POP (point of presence)
- Billing:
 - □ **CIR** (committed information rate)
 - MAR (maximum allowable rate) DE (discharge eligible)





- Types of packet-switched services
 - Frame relay
 - Ethernet
 - MPLS



Frame relay

- Flexible layer 2 standard for encapsulation and packetswitching in WANs
- Still common, but usage is declining
- Designed for high performance and efficiency
- Does not provide error control (unreliable)

Flags (1 bytes)	Address (2 bytes)	Data (variable)	Frame Check Sequence (2 bytes)	Flags (1 bytes)	
--------------------	-------------------------	--------------------	---	--------------------	--



Ethernet

- Converting to and from LAN/BN protocols and WAN protocols slows communication
- Many carriers have switched or are switching to Ethernet for WANs
- These new packet services bypass the public switched telephone network (PSTN)
- May be less expensive than other alternatives



Multiprotocol label switching (MPLS)

- Can be used with a variety of layer 2 protocols
- Label is applied when entering carrier network between layer 2 and layer 3 headers
 - MPLS is sometimes called a layer 2.5 protocol
- Label is used in forwarding decisions and traffic engineering
- Packets can be switched using labels faster than using complete IP addresses and routing tables





- Movement towards IP Services
 - Telecommunications companies are moving towards "all IP" networks
 - Replacing PSTN networks
 - Ethernet and MPLS commonly used in these networks




Virtual Private Networks (VPNs)

- Provide equivalent of private packet-switched network over the public Internet
- Creates a virtual circuit often called a tunnel
- May use dedicated hardware (VPN gateways) or be implemented in software
- VPNs can be implemented at layer 2 or layer 3




Virtual Private Networks (VPNs)

FIGURE 9-8 A virtual private network (VPN). ISP = Internet service provider



9.4 Virtual Private Networks (VPN)

- □ Lease an Internet connection
- □ VPN gateway (a specially designed router) that allows you to create PVCs = tunnels
- □ VPN client software on clients
- □ Layer 2 VPN (L2TP) or Layer 3 VPN (IPSec)
- □ Tunneling and encryption are two different things
- Advantages: low cost & flexibility
- **Disadvantages:** unpredictable speed & security is a concern





Virtual Private Networks (VPNs)

Intranet VPN

 Provides virtual circuits between organization locations over the Internet

Extranet VPN

- Same as an intranet VPN except that the VPN connects different organizations over the Internet
 - e.g., customers and suppliers


Access VPN

 Enables employees to access an organization's networks from remote locations over the Internet



Virtual Private Networks (VPNs)

FIGURE 9-9 Using VPN software





Virtual Private Networks (VPN)

- Advantages
 - Inexpensive
 - Flexible
- Disadvantages
 - Internet traffic unpredictable
 - Multiple incompatible implementations
 - Not all vendor equipment and services are compatible



WAN Design Practices

Service	Data Rates	Relative Cost	Reliability
Dedicated-Circuit Services			
 T-Carrier 	64 Kbps to 45 Mbps	Moderate	High
• SONET	50 Mbps to 10 Gbps	High	High
Packet-Switched Services			
Frame Relay	64 Kbps to 45 Mbps	Moderate	High
 Ethernet 	1 Mbps to 40 Gbps	Moderate	High
• MPLS	64 Kbps to 10 Gbps	Moderate	High
VPN Services			
• VPN	64 Kbps to 50 Mbps	Low	Moderate



WAN Design Practices

Network Needs	Recommendation
Low to Moderate Traffic (10Mbps or less)	VPN if reliability is less important Frame relay otherwise
High Traffic (10-50 Mbps)	Ethernet or MPLS if available T3 if network volume is stable and predictable Frame relay otherwise
Very High Traffic (50 Mbps – 100 Gbps)	Ethernet or MPLS if available SONET if network volume is stable and predictable



Improving WAN Performance

- Devices
- Circuits
- Demand



Implications for Management

- Shift to Ethernet and MPLS
 - Legacy technologies such as frame relay will be phased out like ATM
 - Cost of WAN hardware and services decreasing
 - Similar to LANs and BNs, WANs are experiencing standardization and commoditization



8.7 Implications for Cyber Security

- WAN most secure part of the network
 - □ VPN without encryption not secure
- Encryption is good
 - □ usually use VPN with encryption in WAN

