



Operating Systems

CSN-232

Dr. R. Balasubramanian

Associate Professor

**Department of Computer Science and Engineering
Indian Institute of Technology Roorkee**


Roorkee 247 667

balarfcs@iitr.ac.in

<https://sites.google.com/site/balaiitr/>



Chapter 1: Introduction





Chapter 1: Introduction

- What Operating Systems Do
- Computer-System Organization
- Computer-System Architecture
- Operating-System Structure
- Operating-System Operations
- Process Management
- Memory Management
- Storage Management
- Protection and Security
- Kernel Data Structures
- Computing Environments
- Open-Source Operating Systems



Operations of CPU


- **Simple loop**

- An instruction is fetched from the memory location specified by the special register called the **program counter**
- The instruction is placed in a special register called the **instruction register**
- The program counter is incremented so it points to the next instruction to be executed
- The instruction decoder – **opcode**
- Depending on the operations, the value of one or more operands can be fetched from memory.



Opcode – operations

- **Movement:** Move a value from one location to another – location may be register or main memory
- **Computation:** operand(s) values to ALU
- **Conditional Branch:** resetting the program counter
- **Procedure call:** Program counter
- **I/O:** Transfer information concerning an input or output operation between the CPU and an I/O device.






Interrupt Handling

- The operating system preserves the state of the CPU by storing registers and the program counter
- Determines which type of interrupt has occurred:
 - **polling**
 - **vectored** interrupt system
- Separate segments of code determine what action should be taken for each type of interrupt





Interrupt Timeline





In Windows and Linux





I/O Structure

- After I/O starts, control returns to user program only upon I/O completion
 - Wait instruction idles the CPU until the next interrupt
 - Wait loop (contention for memory access)
 - At most one I/O request is outstanding at a time, no simultaneous I/O processing
- After I/O starts, control returns to user program without waiting for I/O completion
 - **System call** – request to the OS to allow user to wait for I/O completion
 - **Device-status table** contains entry for each I/O device indicating its type, address, and state
 - OS indexes into I/O device table to determine device status and to modify table entry to include interrupt

Storage Definitions and Notation Review

The basic unit of computer storage is the **bit**. A bit can contain one of two values, 0 and 1. All other storage in a computer is based on collections of bits. Given enough bits, it is amazing how many things a computer can represent: numbers, letters, images, movies, sounds, documents, and programs, to name a few. A **byte** is 8 bits, and on most computers it is the smallest convenient chunk of storage. For example, most computers don't have an instruction to move a bit but do have one to move a byte. A less common term is **word**, which is a given computer architecture's native unit of data. A word is made up of one or more bytes. For example, a computer that has 64-bit registers and 64-bit memory addressing typically has 64-bit (8-byte) words. A computer executes many operations in its native word size rather than a byte at a time.

Computer storage, along with most computer throughput, is generally measured and manipulated in bytes and collections of bytes.

A **kilobyte**, or **KB**, is 1,024 bytes

a **megabyte**, or **MB**, is $1,024^2$ bytes

a **gigabyte**, or **GB**, is $1,024^3$ bytes

a **terabyte**, or **TB**, is $1,024^4$ bytes

a **petabyte**, or **PB**, is $1,024^5$ bytes

Computer manufacturers often round off these numbers and say that a megabyte is 1 million bytes and a gigabyte is 1 billion bytes. Networking measurements are an exception to this general rule; they are given in bits (because networks move data a bit at a time).



Storage Structure


- Main memory – only large storage media that the CPU can access directly
 - **Random access**
 - Typically **volatile**
- Secondary storage – extension of main memory that provides large **nonvolatile** storage capacity
- Hard disks – rigid metal or glass platters covered with magnetic recording material
 - Disk surface is logically divided into **tracks**, which are subdivided into **sectors**
 - The **disk controller** determines the logical interaction between the device and the computer
- **Solid-state disks** – faster than hard disks, nonvolatile
 - Various technologies
 - Becoming more popular




Storage Hierarchy

- Storage systems organized in hierarchy
 - Speed
 - Cost
 - Volatility
- **Caching** – copying information into faster storage system; main memory can be viewed as a cache for secondary storage
- **Device Driver** for each device controller to manage I/O
 - Provides uniform interface between controller and kernel


Simple Device Driver Model



Storage-Device Hierarchy




Registers



Cache

From Computer Desktop Encyclopedia
© 1999 The Computer Language Co., Inc.



Primary Memory (Main Memory)



Memory

7



Solid State Disk





Hard Disk





Optical Compact Disk





Magnetic Tapes





Caching

- Important principle, performed at many levels in a computer (in hardware, operating system, software)
- Information in use copied from slower to faster storage temporarily
- Faster storage (cache) checked first to determine if information is there
 - If it is, information used directly from the cache (fast)
 - If not, data copied to cache and used there
- Cache smaller than storage being cached
 - Cache management important design problem
 - Cache size and replacement policy

Direct Memory Access Structure




- Used for high-speed I/O devices able to transmit information at close to memory speeds
- Device controller transfers blocks of data from buffer storage directly to main memory without CPU intervention
- Only one interrupt is generated per block, rather than the one interrupt per byte



Direct Memory Access Structure


DMA

(Direct Memory Access)




PIO

(Programmed I/O)





How a Modern Computer Works



A von Neumann architecture




Computer-System Architecture

- Most systems use a single general-purpose processor
 - Most systems have special-purpose processors as well
- **Multiprocessors** systems growing in use and importance
 - Also known as **parallel systems, tightly-coupled systems**
 - Advantages include:
 1. **Increased throughput**
 2. **Economy of scale**
 3. **Increased reliability** – graceful degradation or fault tolerance
 - Two types:
 1. **Asymmetric Multiprocessing** – each processor is assigned a specific task.
 2. **Symmetric Multiprocessing** – each processor performs all tasks



Symmetric Multiprocessing Architecture



A Dual-Core Design

- Multi-chip and **multicore**
- Systems containing all chips
 - Chassis containing multiple separate systems

