

```
package currency;

public class CurrencyConverter {

    public void dollarToINR(double dollar) {
        System.out.println("Dollar to INR = " + (dollar * 83));
    }

    public void inrToDollar(double inr) {
        System.out.println("INR to Dollar = " + (inr / 83));
    }

    public void euroToINR(double euro) {
        System.out.println("Euro to INR = " + (euro * 90));
    }

    public void inrToEuro(double inr) {
        System.out.println("INR to Euro = " + (inr / 90));
    }

    public void yenToINR(double yen) {
        System.out.println("Yen to INR = " + (yen * 0.56));
    }

    public void inrToYen(double inr) {
        System.out.println("INR to Yen = " + (inr / 0.56));
    }
}

package distance;

public class DistanceConverter {

    public void meterToKM(double meter) {
        System.out.println("Meter to KM = " + (meter / 1000));
    }

    public void kmToMeter(double km) {
        System.out.println("KM to Meter = " + (km * 1000));
    }

    public void milesToKM(double miles) {
        System.out.println("Miles to KM = " + (miles * 1.609));
    }
}
```

```

    public void kmToMiles(double km) {
        System.out.println("KM to Miles = " + (km / 1.609));
    }
}

```

package time;

```

public class TimeConverter {

    public void hoursToMinutes(double hours) {
        System.out.println("Hours to Minutes = " + (hours * 60));
    }

    public void minutesToHours(double minutes) {
        System.out.println("Minutes to Hours = " + (minutes / 60));
    }

    public void hoursToSeconds(double hours) {
        System.out.println("Hours to Seconds = " + (hours * 3600));
    }

    public void secondsToHours(double seconds) {
        System.out.println("Seconds to Hours = " + (seconds / 3600));
    }
}

```

```

import currency.CurrencyConverter;
import distance.DistanceConverter;
import time.TimeConverter;

```

```

public class Main {

    public static void main(String[] args) {

        CurrencyConverter c = new CurrencyConverter();
        DistanceConverter d = new DistanceConverter();
        TimeConverter t = new TimeConverter();

        System.out.println("==== Currency Converter =====");
        c.dollarToINR(10);
        c.inrToDollar(830);
        c.euroToINR(5);
        c.inrToEuro(450);
    }
}

```

```

c.yenToINR(100);
c.inrToYen(560);

System.out.println("\n===== Distance Converter =====");
d.meterToKM(5000);
d.kmToMeter(5);
d.milesToKM(10);
d.kmToMiles(16.09);

System.out.println("\n===== Time Converter =====");
t.hoursToMinutes(2);
t.minutesToHours(120);
t.hoursToSeconds(2);
t.secondsToHours(7200);
}
}

```

OUTPUT :

===== Currency Converter =====

Dollar to INR = 830.0

INR to Dollar = 10.0

Euro to INR = 450.0

INR to Euro = 5.0

Yen to INR = 56.0

INR to Yen = 1000.0

===== Distance Converter =====

Meter to KM = 5.0

KM to Meter = 5000.0

Miles to KM = 16.09

KM to Miles = 10.0

===== Time Converter =====

Hours to Minutes = 120.0

Minutes to Hours = 2.0

Hours to Seconds = 7200.0

Seconds to Hours = 2.0