Revision Demo Guide

NEST.PH: A Web-Based Integrated Dormitory Management System with VR Room Visualization and Automated Delinquency Escalation Protocol | BSIT 3-5 Group 7

Before you walk in

■ App running with demo data. Open the homepage (***/***) once to check it loads.

■ Open these tabs ahead of time: an **owner/admin** login, a **second admin** login (for Item 5), a **tenant** login, an **approved applicant** who has not paid move-in yet (for Item 3), and a logged-out window.

■ Have at least one whole-room listing with a **room area** filled in, and a few months of payments and expenses so the forecast has history to show.

■ Bring the printed revision matrix. Each item takes about a minute: show it, point at the result, move on.

Panelist 1: Prof. Iluminada Vivien R. Domingo, DBA

1. Generic NEST.PH landing page with a contact option for owners

Panelist's comment: Create a generic application page for other dormitory owners instead of going straight to Pureza Station's page.

LOG IN AS: nobody (logged-out window)

1. Open the homepage ***/***. It shows the NEST.PH platform page, not Pureza Station.

2. Scroll to the embedded YouTube tutorial video.

3. Scroll to **Request NEST.PH for Your Dormitory** and show the form other owners use to contact the team.

4. Click Pureza Station in the dormitory list to show the dorm's own page now comes *after* the platform page.

Point out: Any dormitory owner can find and contact NEST.PH without going through Pureza Station's page.

2. Room area in square meters

Panelist's comment: Include the room area (m²) in the room listing and the VR view, since size affects price.

LOG IN AS: owner, then the logged-out window

1. Owner side: open **Vacancy Monitoring**, edit a whole-room listing and show the **Room area (m²)** field.

2. Public side: open **/rooms** and show the m² on the room card.

3. Open **/vr-tour** for the same room and show the m² in the room details next to the 360° view.

Point out: The owner types in the area and tenants see it in both places. Bed-space rooms are still priced per bed.

3. Two months' deposit + one month advance shown at move-in

Panelist's comment: Show the 2-month security deposit and 1-month advance rent as part of the payment upon signing.

LOG IN AS: approved applicant (has not paid move-in yet)

1. Log in as the approved applicant. The move-in steps open.

2. Go to the **payment type** step and show the **move-in breakdown**: advance rent, security deposit, total.

3. Point at the deposit and show it equals 2 × the full monthly rent (computed automatically).

Point out: The applicant sees exactly what is due upon signing before paying anything.

4. Safety instructions pop-up for emergency tickets

Panelist's comment: Give the tenant an immediate safety step (e.g., use the fire extinguisher), not just "wait for the technician".

LOG IN AS: tenant

1. Go to **My Tickets** and start a new ticket.

2. Choose **Fire / Safety Hazard**. A red safety pop-up appears right away ("Fire or smoke? Get out first.") with numbered steps.

3. Close it and pick **Electrical Issue** to show each emergency type has its own steps (also Plumbing / Water Emergency and Structural Damage).

Point out: The tenant has something safe to do immediately while help is on the way.

5. Several emergencies at once, auto-assigned to online admins

Panelist's comment: Handle many tenants reporting at the same time and make sure an owner/admin is assigned.

LOG IN AS: tenant + two admins (keep both admin tabs open)

1. With both admins logged in, show the **Online** status beside admin names (Tickets page or **Admin Privileges**).

2. From the tenant tab, file an emergency ticket (e.g., Fire / Safety Hazard). File a second one right after, from another tenant if you have one.

3. On the admin **Tickets** page, open each ticket and show it was **assigned automatically** to an online admin.

Point out: Emergencies go to admins who are online, picking whoever has fewer open emergencies, so no one person gets all of them.

Panelist 2: Mr. Mariel Leo T. Violeta, MIT

1. Upload and view the notarized contract: not implemented

Panelist's comment: Provide a way to upload and view the notarized contract.

Nothing to demo. Explain briefly instead:

A contract is valid once there is consent, object and cause (Civil Code Art. 1318), and it binds in any form once those are present (Art. 1356). Notarization only makes it a public document; it does not make it valid. In NEST.PH the tenant signs in the system (consent), the contract names the room/bed and terms (object), and it states the rent and charges (cause).

Optional: open **Lease Contracts** as owner and show a signed contract with these parts. Mention that uploading a notarized copy is a possible future enhancement.

2. Actual values next to forecasted values

Panelist's comment: Show the actual values alongside the forecast (e.g., a second line) so they can be compared.

LOG IN AS: owner

1. Go to **Reports** and pick the **Forecast** report.

2. Show the line chart: the **Actual** line and the **What we forecast** line drawn together.

3. Scroll to the table: each month is labelled **Actual**, **So far** (this month) or **Estimate**, with forecast and actual side by side.

Point out: The owner can see how close the forecast was to what actually happened.

3. Utility costs included in the forecast

Panelist's comment: Include fluctuating electricity and water costs in the forecast.

LOG IN AS: owner

1. Stay on **Reports** → **Forecast** and scroll back to the top of the report.

2. Point at the **Monthly Utilities** card: it shows the lowest to highest utility bill of the last 6 months.

3. Point at the **Expected Expenses** card next to it: under the amount it shows the expense **Range**, which comes from those utility bills.

4. Optional: scroll to **Income vs. expenses** and show the **Forecast expenses** line next to **Forecast income**.

Point out: Forecast expenses follow the real ups and downs of utility bills instead of a fixed amount.

Order tip: do Prof. Domingo's items 1 to 5, then Mr. Violeta's. Items 4 and 5 work as one flow: file the fire ticket (pop-up), then switch to the admin tab (auto-assignment).