Workshop B: Network Configuration Cheat Sheet (Fascicule 1)

Definitions for Fascicule 1

Term Definition

Switch (Commutateur) A device that connects devices within a

network and forwards data based on MAC

addresses.

VLAN A logical grouping of devices in a network,

segmented for better security and

management.

SVI (Switched Virtual Interface)

A virtual interface on a switch used for

routing and remote management.

IP Address A unique identifier for a device on a

network, enabling communication.

Telnet A protocol for remote command-line access

to a network device.

Port Security A feature that restricts access to switch

ports based on MAC addresses.

MAC Address A unique identifier for a device's network

interface used in Layer 2 communication.

VTY (Virtual Terminal Lines) Virtual lines on a switch that allow remote

management via Telnet or SSH.

Default Gateway The IP address of a router used to forward

traffic from the local network to external

networks.

Console Password Password used to access the switch via the

console port for local configuration.

IP Routing The process that enables communication

between different subnets or VLANs.

Secure-down State A port status caused by a port security

violation, where the port is disabled.

MAC Address Table A table on switches that maps MAC

addresses to specific ports for traffic

forwarding.

Static MAC Address A manually configured MAC address

assigned to a specific port on a switch.

Dynamic MAC Address A MAC address learned automatically by a

switch from traffic.

Ping A tool used to test network connectivity by

sending ICMP echo requests and waiting

for a response.

DHCP A protocol that automatically assigns IP

addresses to devices on a network.

1. Basic Configuration of ZC-Switch5

Task	Command	Explanation
Set Hostname	hostname ZC-Switch5	Sets the switch name.
Set Enable Secret Password	enable secret pwdpriv	Encrypts the privileged mode password.
Disable DNS Lookup	no ip domain-lookup	Prevents DNS lookup for invalid commands.
Set MOTD Banner	banner motd 'Authorized users only!'	Sets a message of the day banner.
Set Console Password	line console 0 password pwdconsole login	Sets password for console access.
Set VTY Password	line vty 0 4 password pwdvty login	Sets password for remote Telnet access (VTY lines).
Enable Password Encryption	service password- encryption	Encrypts plaintext passwords in the configuration.

Set Default Gateway ip default-gateway Sets the default gateway for

172.16.10.1 the switch.

Save Configuration write memory Saves the configuration to

memory.

2. Configure VLAN 1 (SVI) on ZC-Switch5

Task Command Explanation

Configure VLAN 1 IP interface vlan 1

Address ip address 172.16.10.253 management interface

255.255.255.0 VLAN 1. no shutdown

Verify Interface Status show ip interface brief Verifies that the VLAN 1

interface is up and configured properly.

from ZC-PC2 to ZC-Switch5.

Configures IP for

3. Enable Telnet Access

Task	Command	Explanation
Configure VTY Lines for Telnet	line vty 0 4 password telnet_password login	Enables Telnet access and sets password for remote login.
Configure MOTD Banner	banner motd 'Authorized access only!'	Sets a message for users accessing the switch remotely.
Save Configuration	write memory	Saves the configuration after enabling Telnet.
Test Telnet	telnet 172.16.10.253	Test the Telnet connection