

Configuring Organisations

User Guide

Access Limited Distribution

PeopleXD Payroll

Table of Contents

Document Control	3
1. Overview.....	4
1.1. Purpose of the Guide.....	4
1.2. What is an Organisation?.....	4
2. Maintain Organisations.....	5
2.1. Copy a Company.....	6
2.1.1. Payroll Parameters.....	7
2.1.2. Payroll Calendar.....	9
2.1.3. Miscellaneous Parameters.....	10
2.2. Edit a Company.....	11
2.3. Add a Company.....	11
2.4. Delete a Company	11
3. Menu Options Required	13

Document Control

Version	Date	Author	Details
1.0	30 th Nov 2019	Brian O'Keeffe	Published to Access LMS
1.1	18 th Jan 2024	James Martin	Formatting update
1.2	23/02/2024	James Martin	Added Sections: 2.1.1 Payroll Parameters 2.1.2 Payroll Calendar 2.1.3 Miscellaneous Parameters

1. Overview

1.1. Purpose of the Guide

The purpose of this document is to provide guidance on how to configure an organisation.

Items covered include how to:

- Add an Organisation.
- Edit an Organisation.
- Duplicate an Organisation.
- Delete an Organisation.

1.2. What is an Organisation?

An organisation may be made of one or more individual companies which operate independently of each other. To distinguish between the different companies and how they operate for payroll, each organisation can configure multiple companies, with unique company codes.

Organisations and their individual companies are also linked directly to pay groups. Each company may have multiple pay groups configured. To have access to a pay group, you must also have access to the company.

2. Maintain Organisations

To add, edit, copy or delete an Organisation:

1. On the **Payroll Dashboard** click the **Settings** tab.
2. In the Company Parameters section click **Organisations**.

Organisations

Code1115Select DetailChoose

Name *Anvils LTD

Address *

10 Main Street

Chesington Hills

Bretherington

Registered No

Contact

Phone No

Fax No

Interface Company

Email Address

Currency Code

Payroll ProviderChoose

Country Code

Employee UDF Identifier

Company UDF Identifier

Revenue Details

Ros P45 Unit No

The following organisation details can be configured or maintained:


- Name
- Address/Contact Details
- Company Registered Number
- Revenue Details
- Pay Periods
- Associated Pay Codes
- Bank Details
- Payroll Calendar

2.1. Copy a Company

Copying an existing company is best practice when creating a new company. This is because it cuts down on the processing time as you may only need to amend a few fields, i.e. Company Code, Contact Details etc.

To copy a Company:

1. Go to the *Organisations* screen.
2. Select a **Company** from the *Code* drop-down list and press **Enter/Tab**.
3. Click **Copy Company**.
4. Enter a **To Company Code**. This will be the code used for the new company.



5. Click **OK**.
6. The following fields should be updated as required.

Optional Field	Description
Registered Number	Enter the company registered number.
Contact	Enter the main company point of contact.
Phone No.	Enter the main company phone number.
Fax No.	Enter the main company fax number.
Interface Company	Enter the ledger interface company code.
Email Address	Enter the main company email address
Currency Code	Select the default currency code. This can be used for converting payments to overall company base currency.
Payroll Provider	Select the main payroll provider from the drop-down menu. To ensure the organisation is not set as international, the payroll provider must be set as CorePay or left blank.

Optional Field	Description
Country Code	Select the Country Code from the drop-down menu.

- Click **Save**.
- Further details can be configured for the company using the *Select Detail* drop-down menu.

The screenshot shows the 'Organisations' configuration page. On the left, there are input fields for 'Code' (1115), 'Name' (Anvils LTD), and 'Address' (10 Main Street, Chesington Hills, Bretherington). On the right, a 'Select Detail' dropdown menu is open, displaying a list of options: 'Choose', 'Payroll Parameters' (which is highlighted in blue), 'Payroll Calendar', 'Miscellaneous Parameters', and 'Bonus Parameters'.

2.1.1. Payroll Parameters

Further Organisation details can be configured in the Payroll Parameters section. The Payroll Parameters section can also be accessed from:

- Payroll Dashboard > Settings > General settings*

The following fields on the payroll parameters screen are mandatory:

Field	Description
General Settings	
Company Code	Enter the Company Code
Payroll Period	Enter the Current Payroll Period
Pay Periods	Enter the number of Pay Periods
Pay Codes	
PAYE	Enter a Pay code for PAYE
NI/PRSI EE	Enter a Pay code for NI/PRSI EE
NI/PRSI ER	Enter a Pay code for NI/PRSI ER
NI/PRSI EE Exempt	Enter a Pay code for NI/PRSI EE Exempt
Salary	Enter a Pay code for Salary
Nett Pay	Enter a Pay code for Nett Pay
PAYE Override	Enter a Pay code for PAYE Override

Field	Description
NI/PRSI EE Override	Enter a Pay code for NI/PRSI EE Override
NI/PRSI ER Exempt	Enter a Pay code for NI/PRSI ER Exempt
Basic Pay	Enter a Pay Code for Basic Pay
Banking Details	
Sort Code	Enter the Bank sort code for the Company
Account No	Enter the Bank account number for the company
User ID	Enter the Bank User ID for the Company
Username	Enter the Paypath Username
Maintain Payroll Parameters	
Academic Start Year	Enter the Academic start year
Academic End Year	Enter the Academic end year
Validate Cost Centre	Enter Y to Validate and N if the cost centre is not to be validated
PAYE Standard Rate	Enter the PAYE standard Rate
PAYE Higher Rate	Enter the PAYE higher rate
PAYE Marginal Rate	Enter the PAYE marginal rate
Child Allowance Limit	Enter the maximum age for child allowance eligibility
Job Share Multiplier	Enter Factor for paying Job sharers
Allocate Salary Cost	Enable Toggle
Advance Pay Cleardown	Enable Toggle
ER PRSI Relief % for EE Pension	Enter the appropriate Employer PRSI relief percentage for Employee pension contributions
Negative Nett Recovery	Enter the Pay code for negative nett recovery
Employer NI Codes	
Cost Centre	Enter the Cost Centre code for posting Employer PRSI
Location	Enter the Location for posting Employer PRSI
Expense	Enter the Expense to be used for posting Employer PRSI
Employer Pension Codes	
Cost Centre	Enter the Cost Centre for Posting Employer Pension
Location	Enter the Location for posting Employer Pension

Field	Description
Expense	Enter the Expense to be used for posting Employer Pension
Payment Control Account	
Cost Centre	Enter the Cost centre code for posting payment control account
Expense	Enter the expense to be used for posting payment control account
Pay Codes	
Withhold Tax	Enter the Pay code for Withholding Tax
Pensionable Salary	Enter the Pay code for Pensionable Salary
Advance Pay	Enter the pay code for Advance pay

Maintain Payroll Parameters
Payroll Dashboard > Organisations > Maintain Payroll Parameters

[Next Page](#)

General Settings

Company Code: Payroll Period: Pay Periods*:

Previous 1 of 1 Next Query

Pay Codes

PAYE	PAYE Override
PAYE	PAYE Override
NI EE	NI EE Override
Employee NI	Employee NI Override
NI ER	NI ER Override
Employer NI	Employer NI Override

2.1.2. Payroll Calendar

A payroll calendar must be maintained for each company within an organisation. The following points should be noted:

- The calendar consists of the year broken up into week numbers, e.g. 202001, 202002, 202003 etc.
- The calendar tracks the period end date for weekly, fortnightly, and four-weekly pay groups. The period end date for monthly pay groups will always be the last day of the month.
- The payroll calendar does not track the payment date.

PeopleXD Payroll: Configuring Organisations

- Period end dates can be offset at a pay group level.
- The calendar will always contain at least the current year and future years.

Further Details can be found on the [Configuring Payroll Calendar User Guide](#).

Maintain Payroll Calendar
Payroll Dashboard > Organisations > Maintain Payroll Calendar

Calendars

Company
8015 Baseline UK Company

Amend Dates

Build / Rebuild Year

Week Number	Tax Period	Calendar Period	Week End Date	Production Week	Mth. Seq.	Qtr. Seq.	FNtly Ind.	4 Wkly Ind.	Mont... Ind.	Multi Run	
201801	201801	201804	07-Apr-2018	201801	1	1	N	N	N		...
201802	201801	201804	14-Apr-2018	201802	2	2	Y	N	N		...
201803	201801	201804	21-Apr-2018	201803	3	3	N	N	N		...
201804	201801	201804	28-Apr-2018	201804	4	4	Y	Y	Y		...
201805	201802	201805	05-May-2018	201805	1	5	N	N	N		...
201806	201802	201805	12-May-2018	201806	2	6	Y	N	N		...
201807	201802	201805	19-May-2018	201807	3	7	N	N	N		...
201808	201802	201805	26-May-2018	201808	4	8	Y	Y	Y		...

2.1.3. Miscellaneous Parameters

Further Organisation details can be configured in the Miscellaneous Parameters section. The Miscellaneous Parameters section can also be accessed from:

- *Payroll Dashboard > Settings > Company Parameters> Other General settings*

Maintain Miscellaneous Parameters
Payroll Dashboard > Organisations > Maintain Miscellaneous Parameters

Other General Settings

Company
Baseline UK Company

Country
UK

Tax Credits

Shorter Working Year Payment Pay Code

Shorter Working Year Deduction Pay Code

Parental Leave Payment Pay Code

Parental Leave Deduction Pay Code

Part Time Claims/Irregular Payments

SSP Recovered

Inland Revenue Paypath Reference
MUST BE POPULATED FOR UK COMPANY

2.2. Edit a Company

 Note:

Company details should not be edited during a payroll run.

To edit a Company:

1. Go to the *Organisations* screen.
2. Select a **Company** from the *Code* drop-down list and press **Enter/Tab**.
3. Click the field to be amended and enter the data, i.e. Change the address field in the event of a company moving premises.
4. Click **Save**.

2.3. Add a Company

It is best practice to copy a company, however if you need to add a new company from scratch:

1. Click **Add**.
2. Enter a **Company Code** in the *Code* field (Max. 40 Characters).
3. Enter a **Name**.
4. Enter a **Company Address**.

2.4. Delete a Company

Companies should only be deleted if it has been created in error and payroll has not been run using it. To delete a Company created in error:

1. Go to the *Organisations* screen.
2. Select a **Company** from the *Code* drop-down list and press **Enter/Tab**.
3. Click **Delete**.
4. Click **Save**.

**Note:**

If you delete a company, all active pay groups assigned to that company will need to be amended/assigned a new company. To do this:

1. On the **Payroll Dashboard** click the **Settings** tab.
2. In the Codes section click **Pay Groups**.
3. Select a **Pay Group**.
4. Select a company from the *Company Reference* drop-down menu.
5. Click **Save**.
6. Repeat for each Pay Group affected.

3. Menu Options Required

The following menu option is required for an employee to access the *Organisations* screen from the Settings tab.

Menu Option	System
Settings – Organisations	CorePortal Pay
Settings - Calendars	CorePortal Pay
Settings - General Settings	CorePortal Pay
Settings - Other General Settings	CorePortal Pay