

Disk Exchange (Back Office)

User Guide

Access Limited Distribution

PeopleXD Payroll

Table of Contents

Document Control	4
1. Overview.....	5
1.1. Disk Exchange.....	5
1.2. Overview.....	5
2. Disk Exchange.....	6
2.1. Maintain Data Load Control	6
2.2. Load Deductions File	7
2.2.1. Load Normal Deductions	8
2.2.2. Load Pension Scheme.....	8
2.2.3. Select the file to be loaded.....	9
2.2.4. Data Errors	9
2.3. Amend Loaded Data.....	10
2.3.1. Global Delete.....	11
2.4. Update Deduction/Pension Details.....	11
2.4.1. Update Normal Deductions	11
2.4.2. Update Pension Schemes	13
2.5. Run Data Load Validation	15
2.6. Generate Output Deductions File	17
3. Appendix.....	19
3.1. Load Deductions - File Layout and Naming Convention	19
3.1.1. File Name	19
3.1.2. File Format:.....	19
3.2. Generate Output Deductions - File Layout and Naming Convention.....	19

Table of Contents

3.2.1. File Name.....	19
3.2.2. File Format.....	20
3.3. Software List.....	21
3.3.1. Forms	21
3.3.2. Reports.....	21

Document Control

Version	Date	Author	Details
1.0	11 th May 2023	Isabelle Grey	Published to the Customer Success Portal.

1. Overview

1.1. Disk Exchange

This document provides guidance on using Disk Exchange. This includes steps used to:

- Maintain Data Load Control
- Load Deductions File
- Amend Loaded Data
- Update Deduction/Pension Details
- Run Data Load Validation
- Generate Output Deductions File

1.2. Overview

The disk exchange module allows you to accept a file of deduction details (Pay Codes or Pension/AVC Schemes) from a third party in a [specified format](#) and load these into payroll.

It also allows you to generate a file of deductions taken from employees and return them to a third party in a specified format.

2. Disk Exchange

To access the disk exchange module:

1. Go to *CorePay > Employee > Employee Deductions > Disk Exchange*.

There are 6 options available:



Disk Exchange

- ☒ Load Deductions File
- ☐ Amend Loaded Data
- ☐ Update Deduction/Pension Details
- ☐ Maintain Data Load Control
- ☐ Run Data Load Validation
- ☐ Generate Output Deductions File

2.1. Maintain Data Load Control

Click **Maintain Data Load Control** to set up the Pay Codes that may be processed using the Disk Exchange options.

Dept. Id.	Pay Code	Pension Scheme	Value Disk Status I.D.	Last Updated	Upload Status
999999	700 VHI		0		
999999		1 PENSION SCHEME	0		

The fields available are:

Field	Description
Dept Id.	This is a mandatory field and by default can be set to 999999, or some other relevant number.
Pay Code	Enter a valid Deduction Pay Code, list of values supplied.
Pension Scheme	Enter a valid Pension Scheme, list of values supplied.

Field	Description
Value Status	If the values on the file are Periodical then enter '0'. If the values on the file are weekly amounts then enter '1' and these will automatically be converted to the Periodical equivalent. No other value is allowed here.
Disk I.D.	This is a displayed field only and is populated at the Update Stage.
Last Updated	This is a displayed field only and is populated at the Update Stage.
Upload Status	This is a view only field which is used to keep a record of the status of the loaded data. It is updated at each stage of processing i.e. Load, Validation and Update stages. 1. Load Failed 2. Loaded 3. Error/Manual (if an error occurred at Validation stage) 4. Validated (No errors encountered at Validation stage) 5. Updated (Update stage)



Note:

Pay Codes and Pension Schemes must be recorded separately. If you enter a valid Pay Code and a valid Pension Scheme on the same record, the system will produce an error message, which will not allow you to save the record until you clear one of the values out.

2.2. Load Deductions File


The Load Deductions File option loads data from a user specified file on the file system to an intermediate payroll table and produces a validation report.

There are two types of deduction files that can be loaded into the system by clicking the corresponding radio button. See section [3. Appendix](#) for the file format.

2.2.1. Load Normal Deductions

To load normal deductions populate the fields:

1. Click **Load Deductions File**.
2. Enter a *Department* as recorded in Maintain Data Load Control or press return for the default code of 999999.
3. Select **Deduction**.




The screenshot shows a software interface for loading normal deductions. It contains several input fields and radio buttons. The 'Department' field is populated with '999999'. The 'Deduction Type' section has two radio buttons: 'Deduction' (which is selected) and 'Pension'. The 'Pay Code' field is populated with '700' and has a dropdown menu showing 'V.H.I'. The 'Start Date' and 'End Date' fields are empty.

4. Enter a valid *Pay Code* for the Department entered i.e. if the specified Pay Code does not exist on the Maintain Data Load Control screen for the Department entered then the system will not allow you to continue.
5. Optional – Enter a *Start Date*. If specified, this will be the default Start Date to be used on all new deduction records on the incoming file. This field may be left blank, therefore accepting any Start Date that may exist on records in the incoming file.
6. Optional – Enter an *End Date*. If specified, this is the default End Date to be used on all Deduction records now being ended. This field may be left blank, therefore accepting any End Date that may exist on records in the incoming file.
7. [Use the default or select the file to be loaded.](#)
8. Click OK. A message will display and once acknowledged the Disk Exchange - Data Load Report will be produced.

2.2.2. Load Pension Scheme

To load Pension Schemes populate the fields:

1. Click **Load Deductions File**.
2. Enter a *Department* as recorded in Maintain Data Load Control or press return for the default code of 999999.
3. Select **Pension**.



The screenshot shows a dialog box with the following fields and options:

- Department:** A text box containing '999999'.
- Deduction Type:** Two radio buttons, 'Deduction' (unselected) and 'Pension' (selected).
- Pension Scheme:** A list box showing '1 PENSION SCHEME 1'.
- Start Date:** A text box.
- End Date:** A text box.

4. Enter a valid *Pension Scheme Code* for the Department entered i.e. if the specified Pension Scheme does not exist on the Maintain Data Load Control screen for the Department entered then an error will display.
5. Optional – Enter a *Start Date*. If specified, this will be the default Start Date to be used on all new pension records on the incoming file. This field may be left blank, therefore accepting any Start Date that may exist on records in the incoming file.
6. Optional – Enter an *End Date*. If specified, this is the default End Date to be used on all pension records now being ended. This field may be left blank, therefore accepting any End Date that may exist on records in the incoming file.
7. [Use the default or select the file to be loaded.](#)
8. Click OK. A message will display and once acknowledged the Disk Exchange - Data Load Report will be produced.

2.2.3. Select the file to be loaded.

By default, the system will look for the file in the following format:

- IN<Pay Code/Pension Code padded to four places>.DAT

For example for Pay Code 700 by default the system will look for the file IN0700.DAT.

To change the default click *Browse* to use the windows file explorer system to navigate to a desired location and select a file from there.

After the initial run, the system will save this location and provided the file to be loaded is in the same file system directory then there will not be a need to search for the file for future loads.

2.2.4. Data Errors

As the file is loaded, the data is validated and any errors that may have occurred will be reported in the 'Disk Exchange – Data Load' report under the 'Take on Validation Exceptions' heading. The


upload status in 'Maintain Data Load Control' will move to a status of 3 (Error/Manual) indicating that the data did not validate correctly.

If the Data validates correctly then the upload status in 'Maintain Data Load Control' will move to a status of 4 (Validated).

2.3. Amend Loaded Data

All valid data that was loaded into the system may now be viewed/amended to do this click Amend Loaded Data. Records may be deleted but not added.

A facility also exists whereby any records which were deemed to be invalid i.e. status number 3 can be globally deleted from the system before uploading. Invalid record can also be manually deleted if required on an individual basis using this screen.



Employee Reference	Code	Start Date	End Date	Reference	Deduction Value	Annual Value	Stat.
198486	700	08-JUL-2003		0207256	82.65	4297.80	4

The fields available are:

Field	Description
Start Date	This field may be left blank or any valid date may be supplied.
End Date	This field may be left blank or any valid date after the Start Date may be supplied.
Reference	The reference will act as an identifier for the deduction.
Deduction Value	This is the periodic deduction value.
Annual Value	This is the annual amount, if applicable.
Upload Status	This field is display only and will have one of the following values:

Field	Description
	1. Load Failed
	2. Loaded
	3. Error/Manual (if an error occurred at Validation stage)
	4. Validated (No errors encountered at Validation stage)
	5. Updated (Update stage)

2.3.1. Global Delete

The Amend Loaded Data Screen also shows the Department ID on the bottom block for each loaded pay code and Department ID.

A Global Delete facility for all invalid data records is available at the bottom of the Amend Loaded Data section of the screen. This allows you to globally remove all invalid data records for the Selected Pay code and Department ID line item and to automatically proceed to the update option (without having to re-load the data file).

If you want to delete invalid records for a Pay code and Department ID:

1. Select the relevant line.
2. Click **Delete Invalid Records**.
3. Click Y on the confirmation message to delete the records.

2.4. **Update Deduction/Pension Details**

All valid data is now applied to the payroll deduction tables for processing in future payroll runs. The Update Deduction/Pension Details option loads data from a user specified file on the file system to an intermediate payroll table and produces a validation report.

There are two types of deduction files that can be loaded into the system by clicking the corresponding radio button.

2.4.1. Update Normal Deductions

Position 29 of the input file holds the Take-on status of each individual deduction record. There are three categories that the deduction data may relate to:

Take-on Status 1 - Adding a New Deduction

New Deductions will be loaded onto the system for all records with a take-on status of 1.

- If the Pay Code is a Percentage Pay Code and if the Pay code is a Standard Value Pay Code then the Deduction Value will take on the value of the Standard Percentage on the Pay Code, otherwise the Deduction value remains the same as that on the original file.
- If the Pay Code is NOT a Percentage Pay Code, then check the Value Status on the *Maintain Data Load Control* screen.
 - A value status of 0 indicates that the values are periodical and will remain same.
 - A values status of 1 indicates that the values are weekly amounts. These amounts will automatically be converted to the periodical equivalent at this stage.

Take-on Status 2 - Altering a Deduction

Updates existing deductions, changing the values according to the following rules where a take-on status of 2 exists.


- If the Pay Code is a Percentage Pay Code and if the Pay code is a Standard Value Pay Code then the Deduction Value will take on the value of the Standard Percentage on the Pay Code, otherwise the Deduction value remains the same as that on the original file.
- If the Pay Code is NOT a Percentage Pay Code, then check the Value Status on the 'Maintain Data Load Control' screen.
 - A value status of 0 indicates that the values are periodical and will remain same.
 - A values status of 1 indicates that the values are weekly amounts. These amounts will automatically be converted to the periodical equivalent at this stage.

Take-on Status 3 - Ending a Deduction

All Deductions on the file with a take-on status of 3 will be end dated accordingly.

To update normal deductions:

1. Click **Update Deduction/Pension Details**.
2. Enter a *Department* as recorded in Maintain Data Load Control or press return for the default code of 999999.
3. Select **Deduction**.

A screenshot of a software dialog box titled "Pay Code". It contains three fields: "Department" with the value "999999", "Deduction Type" with radio buttons for "Deduction" (selected) and "Pension", and "Pay Code" with the value "700". Below the "Pay Code" field is a list box showing "V.H.I." as the selected option. At the bottom are "OK" and "Cancel" buttons.

Department: 999999

Deduction Type: ☒ Deduction ☐ Pension

Pay Code: 700 V.H.I.

OK Cancel

4. Enter a valid *Pay Code* for the Department entered. The Deduction Pay Code must exist on the *Maintain Data Load Control* screen with a status of 4 (Validated) – in order for the update to run otherwise an error message will display.
5. Click **OK**.

At this point, the Status field on the *Amend Loaded Data* screen has been updated to 5 for individual records indicating that the update has been completed for that particular employee.

The following details are updated on the *Maintain Data Load Control* screen:

- **Upload Status** - Set to 5 to mark as Updated.
- **Disk I.D.** - Disk I.D. (unique date for the file) from the file.
- **Last Updated** - System Date at runtime.

2.4.2. Update Pension Schemes

Position 29 of the input file holds the Take-on status of each individual deduction record. There are three categories that the deduction data may relate to:

Take-on Status 1 – Adding a New Employee Pension Deduction

New Pension Schemes will be loaded onto the system for all records with a take-on status of 1.

If the scheme to be loaded onto the system is set up with a pension type of Pension Scheme, then the scheme will be set up as a Percentage value scheme where Percentage is selected otherwise the scheme will be set up as a normal Deduction scheme.

If the scheme to be loaded onto the system is set up with a pension type of AVC Pension, then the scheme will be set up as an AVC Percentage value scheme where percentage is selected otherwise the AVC Pension will be set up as a standard AVC value scheme.

On the *Maintain Data Load Control* screen:

- A value status of 0 indicates that the values are periodical and will remain same.
- A values status of 1 indicates that the values are weekly amounts. These amounts will automatically be converted to the periodical equivalent at this stage.

Take-on Status 2 – Altering an Existing Pension Deduction

Update existing pension deductions, changing the values according to the following rules where a take-on status of 2 exists.

Where the pension type selected is Pension Scheme, and the scheme is treated as a percentage, then the Override Deduction Percent (EE) 1 field on the pension record will be altered otherwise the Deduction Value (EE) will be altered.

Where the pension type selected is AVC Pension, and the scheme is treated as a percentage, then the AVC Percent on the pension record will be altered otherwise the AVC Value will be altered.

On the *Maintain Data Load Control* screen:


- A value status of 0 indicates that the values are periodical and will remain same.
- A values status of 1 indicates that the values are weekly amounts. These amounts will automatically be converted to the periodical equivalent at this stage.

Take-on Status 3 – End Dating a Pension Deduction

All Deductions on the file with a take-on status of 3 will be end dated accordingly.

To update pension schemes:

1. Click **Update Deduction/Pension Details**.
2. Enter a *Department* as recorded in Maintain Data Load Control or press return for the default code of 999999.
3. Select **Pension**.



The screenshot shows a dialog box with the following fields and options:

- Department:** A text box containing '999999'.
- Deduction Type:** Two radio buttons: ☐ Deduction and ☒ Pension.
- Pension Scheme:** A dropdown menu showing '1' and 'PENSION SCHEME 1'.
- Pension Type:** Two radio buttons: ☒ Pension Scheme and ☐ AVC Pension.
- Value/Percentage:** Two radio buttons: ☒ Value and ☐ Percentage.
- Buttons:** 'OK' and 'Cancel' buttons at the bottom.

4. Enter a valid *Pension Scheme* for the Department entered. The Deduction Pension Scheme must exist on the *Maintain Data Load Control* screen with a status of 4 (Validated) – in order for the update to run otherwise an error message will display.
5. Select the Pension Type:
 - a. Pension Scheme.
 - b. AVC Pension.
6. Select Value or Percentage.
7. Click **OK**.

At this point, the Status field on the *Amend Loaded Data* screen has been updated to 5 for individual records indicating that the update has been completed for that particular employee.

The following details are updated on the *Maintain Data Load Control* screen:

- **Upload Status** - Set to 5 to mark as Updated.
- **Disk I.D.** - Disk I.D. (unique date for the file) from the file.
- **Last Updated** - System Date at runtime.

2.5. Run Data Load Validation

The Run Data Load Validation option produces a validation report for all loaded or manually amended data on the system at any point before the update stage i.e. when the Upload status is at any of the following stages:


- 2 – Loaded
- 3 – Error/Manual
- 4 – Validated

This is the same report that is produced for the *Load Deductions File* option. However, once the data has been manually modified using the *Amend Loaded Data* option, this report needs to be invoked to ensure the changes made are acceptable.

There are two types of deduction files that can be validated against the system by clicking the corresponding radio button.

To run data load validation:

1. Click **Run Data Load Validation**.
2. Enter a *Department* as recorded in Maintain Data Load Control or press return for the default code of 999999.



The screenshot shows a dialog box for data load validation. It contains the following elements:

- Department:** A text field containing the value '999999'.
- Deduction Type:** Two radio buttons. The 'Deduction' radio button is selected, and the 'Pension' radio button is unselected.
- Pay Code:** A text field that is currently empty.
- Buttons:** 'OK' and 'Cancel' buttons at the bottom.

3. Select the Deduction Type:
 - a. Select **Deduction**.
 - i. Enter a valid *Pay Code* for the Department entered. The Deduction Pay Code must exist on the Maintain Data Load Control screen with a status of 2 (Loaded), 3 (Error/Manual) or 4 (Validated) – in order for the validation to run.
 - b. Select **Pension**.
 - i. Enter a valid *Pension Scheme* for the Department entered. The Deduction Pension Scheme must exist on the Maintain Data Load Control screen with a status of 2 (Loaded), 3 (Error/Manual) or 4 (Validated) – in order for the validation to run.
4. Click **OK**.

The status on 'Amend Loaded Data' will be set to 4 (Validated), provided the employee being validated passes all the validation checks and no errors were encountered.

If at this point ALL of the employee records have a status of 4, then the Status on *Maintain Data Load* screen will also be set to 4 (Validated). Otherwise, the Status will be set to 3 – Error/Manual.

2.6. Generate Output Deductions File

The Generate Output Deductions File option allows you to generate a file, per pay group and pay code combination for a range of periods, of deductions taken from employees and allow the user to return the generated details to a third party in a specified format.

To generate the file:

1. Click **Generate Output Deductions File**.

Period From	200301	Period To	200352	Dept Id	999999	Control Totals	Y
Pay Group	10	WEEKLY WAGES					
Pay Code	750	UNION					

2. Enter a *Period From*.
3. Enter a *Period To*. This must be greater than the start period specified.
4. Enter a *Department* as recorded in Maintain Data Load Control or press return for the default code of 999999.
5. Populate the *Control Totals* field:
 - a. **Y** - For a control total/trailer record to be included in the output file and the output report.
 - b. **N** - If a control total/trailer record is not required then either leave blank or enter N.
6. Enter a valid *Pay Group*.
7. Enter a valid *Pay Code*.
8. Click Browse to select the file location for the output file.

**Note:**

Once a location has been selected on the initial run, the system will save this information and all future runs will save the files to the exact same folder. If a new location is required, then use the browse button once again to select the new location.

9. Click **OK**.
10. Click **OK** on the confirmation message. The *Disk Exchange – Output Listing* will display.
11. Navigate to the file location selected to retrieve the file.

An output file will be produced for each combination of Pay Group and Pay Code that exists at runtime.

By default, the system will produce a file in the following format:

- OUT<Pay Code/Pension Code padded to four places concatenated with the Pay Group padded out to four places>.DAT.
- For example for Pay Group 10 and Pay Code 750 the output file produced is called OUT07500010.DAT and will be saved to the C:\ drive.

Navigate to the c:\ drive and the file is ready to be sent to the third party company involved.

3. Appendix

3.1. Load Deductions - File Layout and Naming Convention

3.1.1. File Name

IN<Pay Code/Pension Code padded to four places>.DAT

For example to load Pay Code 700 by default the system will look for the file IN0700.DAT.

3.1.2. File Format:

Detail Record:

Name	Size	Type	Position
Pay Code	4	Numeric	1-4
Disk I.D.	8	Date	5-12
Start Date	8	Date	13-20
End Date	8	Date	21-28
Take on Status	1	Numeric	29-29
Employee Reference	10	Character	30-39
Deduction Value	8	Numeric (value in pence)	40-47
Annual Value	10	Numeric (value in pence)	48-57
Reference	12	Character	58-69
Department I.D.	6	Numeric	70-75

3.2. Generate Output Deductions - File Layout and Naming Convention

3.2.1. File Name

OUT<Pay Code/Pension Code padded to four places concatenated with the Pay Group padded out to four places>.DAT

For example for Pay Group 10 and Pay Code 750 the output file produced will be called OUT07500010.DAT.

3.2.2. File Format**Detail Record:**

Name	Size	Type	Position
Department I.D.	6	Numeric	1-6
Pay Group	4	Numeric	7-10
Pay Code	4	Numeric	11-14
Employee Reference	10	Characters	15-24
Forename	15	Characters	25-39
Surname	15	Characters	40-54
Start Date	8	Date	55-62
End Date	8	Date	63-70
Value	10	Numeric (value in pence)	71-80
Cumulative Value	10	Numeric (value in pence)	81-90
Spaces	19	Spaces	91-109
Account Code	12	Characters	110-121

Control/Trailer Record (if applicable):

Name	Size	Type	Position
Department I.D.	6	Numeric	1-6
System Date	8	Date	7-14
Total Value	13	Numeric (value in pence)	15-27
Cancellations Value	13	Numeric (value in pence)	28-40
Employee Count	6	Numeric	41-46
Cancellations	6	Numeric	47-52
Total Count	6	Numeric	53-58

3.3. Software List

3.3.1. Forms

Pay7300.fmx - Disk Exchange [Ver.09]

3.3.2. Reports

Payb7304.rep - Disk Exchange - Data Load

Payb7306.rep - Disk Exchange - Updated Deduction Data

Payb7310.rep - Disk Exchange Output Listing