

Configuring the Organisational Structure

User Guide

Access Limited Distribution

People Management

Table of Contents

Document Control	4
1. Overview	5
1.1. Purpose of the Guide.....	5
2. How to Configure	6
2.1. Where to access the Organisational Structure.....	6
2.2. Add a New Organisational Structure.....	8
2.2.1. Create the Structure	8
2.2.2. Add Levels to the Structure	10
2.2.3. Define Reference Data Items.....	12
2.2.4. Hierarchy Indicator	13
2.2.5. Initial Value.....	16
2.2.6. Hide Indicator	18
2.2.7. Display Mode	20
2.2.8. Activate the Organisational Structure.....	22
2.3. Edit an Existing Organisational Structure	24
2.3.1. How to Add a Level.....	25
2.3.2. How to Remove a Level.....	27
2.3.3. How to reorder a level.....	30
2.4. Organisational Structure Reference Data.....	31
2.4.1. Company	33
2.4.2. Division	33
2.4.3. Management Unit.....	34
2.4.4. Department.....	36

Table of Contents

2.4.5. Work Group.....	38
2.4.6. Cost Centre.....	38
2.4.7. Location.....	40
2.4.8. User Fields 1 – 5.....	41
2.5. Linking the Hierarchy	43
2.5.1. How to access the Hierarchy Maintenance	44
2.5.2. Creating a Hierarchy.....	48
2.5.3. Add a Company / Initial Level	50
2.5.4. Add Levels to the Hierarchy.....	53
2.5.5. Remove a Level.....	57
2.5.6. Shared Hierarchy Elements	58
2.6. Other Configuration Options	59
2.6.1. Default to Collapse / Expand Hierarchy Display	59
2.7. Menu Options	60
2.7.1. Organisational Hierarchy	60
2.7.2. Company Reference Data	61
2.7.3. Management Unit.....	61
2.7.4. Department.....	61
2.7.5. Division	61
2.7.6. Location.....	61

Document Control

Version	Date	Author	Details
1.0	16 th Dec 2019	Peter Travers	Published to Access LMS

1. Overview

1.1. Purpose of the Guide

The purpose of this guide is to provide detailed guidance on how to manage the Organisational Structure & Organisational Hierarchy configuration on CoreHR.


This includes:

- Creating a new Organisational Structure.
- Editing an existing Organisational Structure.
- Creating or updating the reference data that is used specifically by the Organisational Structure.
- Creating or updating the linked Organisational Hierarchy.


2. How to Configure

2.1. Where to access the Organisational Structure

The Organisational Structure is managed in the CoreHR back-office application. To access this: Go to *CorePersonnel* > *Maintenance* > *Post Management* and select **Organisational Hierarchy**.



The *Maintain Hierarchy Structure* screen opens.



- All existing Organisational Structures are listed on screen.

- For a new implementation, there will always be 1 record here at a minimum i.e. the default Organisational Structure.

The *Structure Code* filter at the top of the screen provides the ability to restrict the records shown on screen to the chosen *Structure Code*. This is set to "All" by default.

From this screen, it is possible to:

- View an existing Org Structure and the corresponding linked hierarchy.
- Edit an existing Org Structure and the corresponding linked hierarchy.
- Access reference data maintenance screens for Org Structure levels.
- Create a new Org Structure and the corresponding linked hierarchy.

2.2. Add a New Organisational Structure

2.2.1. Create the Structure

To add a new *Organisational Structure*:

1. Go to *CorePersonnel > Maintenance > Post Management* and select **Organisational Hierarchy**.

The *Maintain Hierarchy Structure* screen opens.

2. Click the **Add New Structure Code** button.

The screenshot shows the 'Maintain Hierarchy Structure' window. At the top, there's a menu bar with 'AC...', 'E...', 'BL...', 'Field Rec...', 'Qu...', 'H...', 'To...', and 'Wind...'. Below the menu bar is a toolbar with various icons. The main area has a 'Structure Code' dropdown set to 'All'. To the right of the dropdown are two buttons: 'Add New Structure Code' (highlighted with a red box) and 'Add New Structure'. Below this is a table titled 'Hierarchy' with columns: 'Structure Code', 'Hierarchy Name', 'Effective Date', 'Date Applied', 'Edit', 'View', and 'Data'. The table contains one row with '1' in the 'Structure Code' column, 'CUSTOMER GROUP NAME' in the 'Hierarchy Name' column, '09-AUG-2008' in the 'Effective Date' column, and '17-SEP-2012' in the 'Date Applied' column. There are also buttons for 'Edit', 'View', and 'Data' for each row.

3. The *Maintain Hierarchy Structure Code* opens. Any existing *Structure Codes* will be displayed here.

To add a new *Structure Code*.

- a. Provide a *Code* (up to 6 alphanumeric characters).
- b. Provide a *Description* (up to 40 alphanumeric characters).
- c. Click the  button to save changes.

Structure Code	Description	Analysis Code	Description
1	CUSTOMER GROUP NAME		
ABC	ABC SOLUTIONS		

- d. Click the  to close the window.
- e. Back on the *Maintain Hierarchy Structure* click the **Add New Structure** button.

Structure Code	Description	Hierarchy Name	Effective Date	Date Applied	Edit	View	Data
1	CUSTOMER GROUP NAME	CoreHR	09-AUG-2008	17-SEP-2012	Edit	View	Data
					Edit	View	Data
					Edit	View	Data

- f. The *Add New Hierarchy Structure* screen will pop up.
- g. Select a *Structure Code*, by clicking the  button for to access the list of all available *Structure Codes*.

The code just created should be available here.

This list will displays active Structure Codes that have not been linked to any other Organisational Structures on the system.

Add New Hierarchy Structure
Maintain Hierarchy Structure

Structure Code: ?

Description:

Available Fields

Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode	Reference
				☐	☐	Description	Reference
				☐	☐	Description	Reference
				☐	☐	Description	Reference
				☐	☐	Description	Reference
				☐	☐	Description	Reference
				☐	☐	Description	Reference
				☐	☐	Description	Reference
				☐	☐	Description	Reference
				☐	☐	Description	Reference
				☐	☐	Description	Reference
				☐	☐	Description	Reference

Save And Close Save Cancel Clear Activate

h. Add a *Description*.

Maximum of 30 alphanumeric characters.

i. Click the **Save** button.

2.2.2. Add Levels to the Structure

The following levels are mandatory on CoreHR and must be included on all Organisational Structures that are defined on the system:

- Company
- Management Unit
- Department
- Cost Centre
- Location
- Work Group

All other available fields are optional i.e.

- Division
- User Field 1 – User field 5

People Management: Configuring the Organisational Structure

The Organisational Structure levels may be configured to include any levels (all mandatory levels must be included) in any order, based on an organisation's individual requirements.

To add a level:

1. Click on the level in the Available Fields list at the left of the screen. The level will be highlighted in blue, as per the screenshot below.

The screenshot shows a table with the following columns: Available Fields, Org Structure, Label, Initial Value, and Description. The 'Company' row is highlighted in blue.

Available Fields	Org Structure	Label	Initial Value	Description
Company				
Division				
Management Unit				
Department				
Cost Centre				
Location				

2. Click on the first yellow box for the required row i.e. the box highlighted in the screenshot below.

The Org Structure and Label field will update to display the selected level.

The screenshot shows the same table as before, but now the 'Company' row is selected, and the 'Org Structure' field is updated to 'ORGZ'. The 'Label' field is also updated to 'Company'.

Available Fields	Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode
Company	ORGZ	Company					Description Reference
Division							Description Reference
Management Unit							Description Reference
Department							Description Reference

3. Repeat as required for all levels, ensuring all mandatory levels have been included.

Available Fields	Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode	Reference
Company	ORGZ	Company			☐	☐	Description	Reference
Division	DIV	Division			☐	☐	Description	Reference
Management Unit	MGU	Management Unit			☐	☐	Description	Reference
Department	DEPT	Department			☐	☐	Description	Reference
Cost Centre	COST	Cost Centre			☐	☐	Description	Reference
Location	LOC	Location			☐	☐	Description	Reference
Work Group	WRKGRP	Work Group			☐	☐	Description	Reference
User Field 1					☐	☐	Description	Reference
User Field 2					☐	☐	Description	Reference
User Field 3					☐	☐	Description	Reference
User Field 4					☐	☐	Description	Reference
User Field 5					☐	☐	Description	Reference

4. It is possible to update the label for some of these levels, if required. This may be useful to ensure that the levels displayed to the user on screen are meaningful and reflect an organisation's terminology, when managing Post Profiles and Contracts e.g. to change the text from *Company* to *Legal Entity*.
 - This is possible for most levels that are defined.
 - The following levels cannot be relabelled:
 - Department
 - Cost Centre
 - Work Group
 - Up to 20 alphanumeric characters may be used.
5. Click on the **Save** button at the end of the screen.

2.2.3. Define Reference Data Items

Ensure that all required Reference Data items have been defined. These will be required to:

- Create the linked hierarchy levels.

People Management: Configuring the Organisational Structure

- Set an initial value.

See [2.4 Organisational Structure Reference Data](#) for further details on how to create and maintain Organisational Structure Reference Data items.

2.2.4. Hierarchy Indicator

The *Hierarchy Indicator* must be enabled for all the levels that will be linked together to form the linked Organisational Hierarchy.

For example, in the screenshot below, the first four levels have the *Hierarchy Indicator* enabled i.e. Company, Division, Management Unit and Department.

Add New Hierarchy Str...

Maintain Hierarchy Structure


Structure Code: ABC ? ABC SOLUTIONS

Description: ABC Solutions

Available Fields	Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode
Company	ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Code-Description Reference
Division	DIV	Division			☒	☐	Code-Description Reference
Management Unit	MGTU	Management Unit			☒	☐	Code-Description Reference
Department	DEPT	Department			☒	☐	Code-Description Reference
Cost Centre	COST	Cost Centre			☐	☐	Description Reference
Location	LOC	Location			☐	☐	Description Reference
Work Group	WRKGRP	Work Group			☐	☐	Description Reference
User Field 1					☐	☐	Description Reference
User Field 2					☐	☐	Description Reference
User Field 3					☐	☐	Description Reference
User Field 4					☐	☐	Description Reference
User Field 5					☐	☐	Description Reference

Buttons: Save And Close, Save, Cancel, Clear, Activate

The allows the user to create a linked hierarchy between all these levels i.e.



The indicator will make those levels and all the corresponding Reference Data items that are created for each level, available when defining the linked hierarchy i.e. ([2.5 Linking the Hierarchy](#)).

- If the level isn't flagged here with the *Hierarchy Indicator*, it will not be available to link in the hierarchy. For the above screenshot, note that Cost Centre, Location and Work Group are not flagged.
- Levels will be linked in the order displayed on screen i.e. Company *then* Division *then* Management Unit *then* Department. Ensure that the levels have been added in the correct order.

Ultimately, any level that is flagged here, will be displayed on the *Org Structure* step of an employee's contract on People Management, as per screenshot below.

- There will be a defined relationship created on CoreHR for each of these levels (see [2.5 Linking the Hierarchy](#)).
- E.g. If I select Division = *Shared Services*, I will only be able to see Management Units that are in that Division such as *Human Resources* or *IT*.

←

Brian Clifford (000112)

New Appointment

People Management > Employee Search > Brian Clifford (000112) > New Appointment

POST SEARCH

1

Organizational Structure

2

Contract Information

3

Salary Information

Post

502201 - Training Manager

Company *

Division *

Management Unit *

Department *

Abc Solutions

Shared Services

Human Resources

HR3 - Training

Cost Centre

Location

Work Group

Cost Centre*

Location*

Work Group*

corehr

Smarter HR Technology

NEXT

2.2.5. Initial Value

The *Initial Value* field provides the ability to set a default value for a level that is always populated on a Post Profile record.

The screenshot shows the 'Add New Hierarchy Structure' dialog box. The 'Maintain Hierarchy Structure' section is active. The 'Structure Code' is 'ABC' and the 'Description' is 'ABC SOLUTIONS'. The 'Available Fields' list on the left includes Company, Division, Management Unit, Department, Cost Centre, Location, Work Group, and five User Fields. The main table lists these fields with their corresponding 'Initial Value' and 'Description'. The 'Company' row is highlighted, and its 'Initial Value' field is set to '1000' and its 'Description' field is set to 'ABC SOLUTIONS'. The 'Hierarchy Indicator' is checked for the Company, Division, Management Unit, and Department levels. The 'Display Mode' is set to 'Code-Description' for the first four levels and 'Description' for the remaining levels. The 'Reference' column shows a reference icon for each level. The 'Save And Close', 'Save', 'Cancel', 'Clear', and 'Activate' buttons are at the bottom.

Available Fields	Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode	Reference
Company	ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Code-Description	
Division	DIV	Division			☒	☐	Code-Description	
Management Unit	MGTU	Management Unit			☒	☐	Code-Description	
Department	DEPT	Department			☒	☐	Code-Description	
Cost Centre	COST	Cost Centre			☐	☐	Description	
Location	LOC	Location			☐	☐	Description	
Work Group	WRKGRP	Work Group			☐	☐	Description	
User Field 1					☐	☐	Description	
User Field 2					☐	☐	Description	
User Field 3					☐	☐	Description	
User Field 4					☐	☐	Description	
User Field 5					☐	☐	Description	

For example, if the *Company* is always “1000 – ABC Solutions”, then setting this as an *Initial Value* will ensure that is defaulted on all Post Profiles created against this Organisational Structure.

Post Profile Maintenance
People Management > View All > Post Profile Maintenance > Post Profile Maintenance

Post Profile

Post Title: CTO
Post Name: Chief Technology Officer
Post Number: 502198
Effective Date: 01-Jan-1990
Post Profile Type: Permanent
Managers Order:
Structure Code: Abc Solutions
Auto Authorisation: ☒
Auto Commencement: ☐
Post Status: Active
Select Option: Post Profile

Hierarchy Definition

Company: 1000 (Abc Solutions)
Division: 1000 (Senior Management)
Management Unit: SMGT (Senior Management)

oorehr
Smarter HR Technology

- The *Initial Value* can be set for any level included in the Organisational Structure.
- Reference Data items need to be configured for the level, for these to be available to select.

To set an *Initial Value*:

1. For the required level, click the  button next to the *Initial Value*.
2. Select the required reference data item from the list available.
3. Click **OK**.

The reference data item will be displayed on the Organisational Structure screen.

4. Click the **Save** button to save.

2.2.6. Hide Indicator

The *Hide Indicator* may be used to hide a level from the user on the post profile and contract screens on CoreHR.

This is typically used where a level is mandatory on the system, but it is not required for an organisation's definition of their Org Structure for their implementation. The system mandatory levels are Company, Management Unit, Department, Cost Centre, Location and Work Group.

To hide a level:

1. Select the *Hide Indicator*.

The screenshot shows the 'Add New Hierarchy Structure' window. The 'Maintain Hierarchy Structure' section is active. The 'Structure Code' is 'ABC' and the 'Description' is 'ABC SOLUTIONS'. The 'Available Fields' list on the left includes Company, Division, Management Unit, Department, Cost Centre, Location, Work Group, and five User Fields. The main table lists these fields with their respective labels, initial values, descriptions, hierarchy indicators, and hide indicators. The 'LOC' (Location) row is highlighted with a red box, and its 'Hide Indicator' checkbox is checked. The 'Initial Value' for 'LOC' is set to '1'.

Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode
ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Code-Description
DIV	Division			☒	☐	Code-Description
MGTU	Management Unit			☒	☐	Code-Description
DEPT	Department			☒	☐	Code-Description
COST	Cost Centre			☐	☐	Description
LOC	Location	1	HEAD OFFICE	☒	☒	Description
WRKGRP	Work Group			☐	☐	Description
User Field 1				☐	☐	Description
User Field 2				☐	☐	Description
User Field 3				☐	☐	Description
User Field 4				☐	☐	Description
User Field 5				☐	☐	Description

2. Set an *Initial Value*.

This is a mandatory step. As the level is mandatory on CoreHR, a default value must be set to ensure that even if the level is hidden on the Post Profile and Contract screens from the user, there is a value set and saved for the record on the system. This will never display to the user but must be stored on the system for all contracts.

3. Click the **Save** button to save the changes.

People Management: Configuring the Organisational Structure

On the Post Profile Maintenance screen, note that the *Location* field is hidden and does not display.

Post Profile Maintenance

Post Profile

Post Title: PA PAYROLL ADMINISTRATOR
Post Number: 502204 Post Status: ACTIVE
Effective Date: 01-JAN-1900
Post Profile Type: P PERMANENT
Managers Order:
Structure Code: ABC ABC SOLUTIONS

Auto Authorisation ☐ Auto Commencement ☐

Hierarchy Definition

Company	1000	ABC SOLUTIONS
Division	1001	SHARED SERVICES
Management Unit	HR	HUMAN RESOURCES
Department	HR4	PAYROLL
Cost Centre	1	DEFAULT
Work Group	HR4	PAYROLL

Select Detail

- 01 - Post Profile
- 02 - Job Profile
- 03 - Plan Appointments
- 04 - View Appointments
- 05 - Competency Profile
- 06 - Sanction History
- 07 - Status Detail
- 08 - Make Dormant/Reactivate
- 09 - Maintain File

Job Description

Comments

On the Contract screen, note that the *Location* field is hidden and does not display.

View Contract

People Management > Employee Search > Bill Kerry (000100) > View Contract

1 Organizational Structure

Post	502204 - Payroll Administrator	Sequence	23
Company *	Abc Solutions		
Division *	Shared Services		
Management Unit *	Human Resources		
Department *	HR4 - Payroll		
Cost Centre	Default		
Location			
Work Group	HR4 - Payroll		

2 Contract Information

oorehr Smarter HR Technology

NEXT

2.2.7. Display Mode

The *Display Mode* setting controls the display of the Org Structure reference data items when creating the linked hierarchy (see [2.5 Linking the Hierarchy](#)).

There are 3 options available:


Option	Display
Description Only the reference data description is displayed.	
Code-Description The level will display using both the reference data code and description in the format: [reference code]-[reference description].	

Description-Code

The level will display using both the reference data code and description in the format:

[reference description]-[reference code].

Hierarchy



2.2.8. Activate the Organisational Structure

Once the new Organisational Structure has been defined on the system, the next step is to 'Activate' it. This is a mandatory step which must be completed to be able to proceed to linking the hierarchy tree.

To activate the Organisational Structure:

1. Click the **Activate** button

Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode	Reference
ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Description-Code	Reference
DIV	Division			☒	☐	Description-Code	Reference
MGTU	Management Unit			☒	☐	Description-Code	Reference
DEPT	Department			☒	☐	Description-Code	Reference
COST	Cost Centre			☐	☐	Description	Reference
LOC	Location	1	HEAD OFFICE	☐	☒	Description	Reference
WRKGRP	Work Group			☐	☐	Description	Reference
USER1	User Field1			☐	☐	Description	Reference
				☐	☐	Description	Reference
				☐	☐	Description	Reference
				☐	☐	Description	Reference
				☐	☐	Description	Reference

2. A pop-up message will require confirmation to proceed. Click **Yes**.

3. Click the **Save** button or **Save and Close** to save changes.

This activation is not automatically saved so the user must also ensure to click **Save** on screen.

The *Date Applied* will reflect the date that the Organisational Structure was activated i.e.

People Management: Configuring the Organisational Structure

Maintain Hierarchy Structure

Structure Code

All

Add New Structure Code

Add New Structure

Hierarchy

Structure Code	Hierarchy Name	Effective Date	Date Applied	Edit	View	Data
ABC	ABC SOLUTIONS	12-SEP-2017	12-SEP-2017	Edit	View	Data
				Edit	View	Data
				Edit	View	Data
				Edit	View	Data
				Edit	View	Data
				Edit	View	Data

2.3. Edit an Existing Organisational Structure


Note: Extra care should be taken when editing an existing structure that is already in use on CoreHR (i.e. this has been used to define Post Profiles and Contract records) as changes made here will have a downstream impact on existing records. Please consult CoreHR in advance of making any amendments, unless absolutely sure of the impact that this will have.

To edit an existing Organisational Structure:

1. Go to *CorePersonnel > Maintenance > Post Management* and select **Organisational Hierarchy**.

The *Maintain Hierarchy Structure* screen opens.

2. Click the **Edit** button next to the structure to be edited



Structure Code	Hierarchy Name	Effective Date	Date Applied	
ABC	ABC SOLUTIONS	12-SEP-2017	12-SEP-2017	Edit View Data

Note: If a linked hierarchy has been defined for the chosen structure, an alert will appear on screen to warn the user that changes made to the structure may have an impact on this linked hierarchy. Click **Yes** to continue to edit.

The *Add New Hierarchy Structure* screen will pop up

Available Fields	Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode
Company	ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Description-Code Reference
Division	DIV	Division			☒	☐	Description-Code Reference
Management Unit	MGTU	Management Unit			☒	☐	Description-Code Reference
Department	DEPT	Department			☒	☐	Description-Code Reference
Cost Centre	COST	Cost Centre			☐	☐	Description Reference
Location	LOC	Location	1	HEAD OFFICE	☐	☒	Description Reference
Work Group	WRKGRP	Work Group			☐	☐	Description Reference
User Field 1	USER1	User Field1			☐	☐	Description Reference
User Field 2					☐	☐	Description Reference
User Field 3					☐	☐	Description Reference
User Field 4					☐	☐	Description Reference
User Field 5					☐	☐	Description Reference

2.3.1. How to Add a Level

For full guidance on how to add a new level to the structure, follow the steps outlined in [2.2.2 Add Levels to the Structure](#).

If adding a new level, consider the following:

- The label may be updated if required to display an organisation's specific terminology e.g. updating "User Field 1" to something more meaningful.
- It is possible to set:
 - [Initial Value](#)
 - [Hierarchy Indicator](#)
 - [Hide Indicator](#)
 - [Display Mode](#) (relevant only if Hierarchy Indicator is enabled)
- Create any new Reference Data required for the new level (see [2.4 Organisational Structure Reference Data](#)).
- If the *Hierarchy Indicator* has been enabled, ensure that the new level is correctly added to the linked hierarchy (see [2.5 Linking the Hierarchy](#))

People Management: Configuring the Organisational Structure

Note: Clicking on the links provided above will jump directly to another section in this document where full detailed guidance is provided on each of the options mentioned.

Add New Hierarchy Structure

Maintain Hierarchy Structure

Structure Code: ?


Description:

Available Fields	Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode	Reference
Company	ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Code-Description	Reference
Division	DIV	Division			☒	☐	Code-Description	Reference
Management Unit	MGTU	Management Unit			☒	☐	Code-Description	Reference
Department	DEPT	Department			☒	☐	Code-Description	Reference
Cost Centre	COST	Cost Centre			☐	☐	Description	Reference
Location	LOC	Location			☐	☐	Description	Reference
Work Group	WRKGRP	Work Group			☐	☐	Description	Reference
User Field 1	USER1	User Field1			☐	☐	Description	Reference
User Field 2					☐	☐	Description	Reference
User Field 3					☐	☐	Description	Reference
User Field 4					☐	☐	Description	Reference
User Field 5					☐	☐	Description	Reference

2.3.2. How to Remove a Level

To remove a level from a structure:

1. Click on the  button which is found at the end of each row for every level.
The level will be cleared on screen.
2. Click the **Save** or **Save and Close** button to save changes.



Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode	Reference
ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Code-Description	Reference
DIV	Division			☒	☐	Code-Description	Reference
MGTU	Management Unit			☒	☐	Code-Description	Reference
DEPT	Department			☒	☐	Code-Description	Reference
COST	Cost Centre			☐	☐	Description	Reference
LOC	Location			☐	☐	Description	Reference
WRKGRP	Work Group			☐	☐	Description	Reference
USER1	User Field 1			☐	☐	Description	Reference
USER2	User Field 2			☐	☐	Description	Reference
USER3	User Field 3			☐	☐	Description	Reference
USER4	User Field 4			☐	☐	Description	Reference
USER5	User Field 5			☐	☐	Description	Reference

It is not possible to create or save an Organisational Structure if gaps / blank rows exist within the hierarchy e.g. as per screenshot below.

- If removing a level creates a blank row in the middle of the hierarchy, this will not save.
- Ensure that further changes are made to reorder levels, to ensure that no gaps exist (see [2.3.3 How to reorder a level](#))


People Management: Configuring the Organisational Structure

Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode
ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Description-Code Reference
DIV	Division			☒	☐	Description-Code Reference
MGTU	Management Unit			☒	☐	Description-Code Reference
DEPT	Department			☒	☐	Description-Code Reference
COST	Cost Centre			☒	☐	Description Reference
LOC	Location	1	HEAD OFFICE	☐	☐	Description Reference
WRKGRP	Work Group			☐	☐	Description Reference
USER1	User Field 1			☐	☐	Description Reference

Please take extra care if removing a level where the *Hierarchy Indicator* is enabled. Removing these levels will have an impact on the linked hierarchy that has been created to include this. For example, if you remove the level “Sub Department” in the below screenshot:

Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode
ORGZ	Company			☒	☐	Description Reference
MGTU	Management Unit			☒	☐	Description Reference
DEPT	Department			☒	☐	Description Reference
USER1	Sub Department			☒	☐	Description Reference
WRKGRP	Work Group			☐	☐	Description Reference
LOC	Location			☐	☐	Description Reference
COST	Cost Centre			☐	☐	Description Reference
USER2	User Field 2			☐	☐	Description Reference
USER3	User Field 3			☐	☐	Description Reference
USER4	User Field 4			☐	☐	Description Reference
USER5	User Field 5			☐	☐	Description Reference

the following pop up will appear:



This will only appear if the level has been included in the linked hierarchy definition. This will not appear if the linked hierarchy has not yet been defined or hasn't included this level as part of the existing definition.

Remember, if removing a level, ensure that the Organisational Structure still includes all mandatory levels (Company, Management Unit, Department, Cost Centre, Location, Work Group) and it will not be possible to save changes to the structure if these are not included.

2.3.3. How to reorder a level

Levels can be reordered on the Organisational Structure by:

- Removing a level to create a gap / blank level.
- Adding a level.

For example, to reorder Work Group and Cost Centre in the below screenshot, the user would need to:

1. Remove Cost Centre.
2. Remove Work Group.
3. Add Cost Centre to the blank row created by removing the Work Group.
4. Add Work Group to the blank row created by removing the Cost Centre.

Add New Hierarchy Structure

Maintain Hierarchy Structure

Structure Code: ?

Description:

Available Fields

- Company
- Division
- Management Unit
- Department
- Cost Centre
- Location
- Work Group
- User Field 1
- User Field 2
- User Field 3
- User Field 4
- User Field 5

Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode
ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Description-Code Reference
DIV	Division			☒	☐	Description-Code Reference
MGTU	Management Unit			☒	☐	Description-Code Reference
DEPT	Department			☒	☐	Description-Code Reference
COST	Cost Centre			☐	☐	Description Reference
LOC	Location	1	HEAD OFFICE	☐	☒	Description Reference
WRKGRP	Work Group			☐	☐	Description Reference
USER1	User Field1			☐	☐	Description Reference
				☐	☐	Description Reference
				☐	☐	Description Reference
				☐	☐	Description Reference
				☐	☐	Description Reference

Buttons: Save And Close, Save, Cancel, Clear, Activate

Please see sections [2.3.2 How to Remove a Level](#) and [2.2.2 Add Levels to the Structure](#) if further guidance is required.

2.4. Organisational Structure Reference Data

Reference Data items must be defined on CoreHR for each of the Organisational Structure levels i.e. the lists of Departments, Cost Centres etc.

Once these have been defined per level, these will be available for selection when:

- Defining the linked hierarchy
- Creating Post Profile records
- Creating new Post Appointment / Contract records

To access the screens required to create new or edit existing reference data items:

1. Go to *CorePersonnel > Maintenance > Post Management* and select **Organisational Hierarchy**.

The *Maintain Hierarchy Structure* screen opens.

2. Click the **Edit** button next to the structure to be edited.

The *Add New Hierarchy Structure* screen opens.

3. Click the **Reference** button that is found at the end of the row for each level.

E.g. to manage Department reference data, click the **Reference** button for the Department row.

Add New Hierarchy Structure

Maintain Hierarchy Structure

Structure Code: ABC ? ABC SOLUTIONS

Description: ABC Solutions

Available Fields	Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode	Reference
Company	ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Code-Description	Reference
Division	DIV	Division			☒	☐	Code-Description	Reference
Management Unit	MGTU	Management Unit			☒	☐	Code-Description	Reference
Department	DEPT	Department			☒	☐	Code-Description	Reference
Cost Centre	COST	Cost Centre			☐	☐	Description	Reference
Location	LOC	Location	1	HEAD OFFICE	☐	☒	Description	Reference
Work Group	WRKGRP	Work Group			☐	☐	Description	Reference
User Field 1					☐	☐	Description	Reference
User Field 2					☐	☐	Description	Reference
User Field 3					☐	☐	Description	Reference
User Field 4					☐	☐	Description	Reference
User Field 5					☐	☐	Description	Reference

Buttons: Save And Close, Save, Cancel, Clear, Activate

In this section, each level will be reviewed in detail as depending on the level required, the Reference Data screens may differ.

2.4.1. Company

Note: The Company reference data is typically managed as part of Payroll Configuration. It is recommended to refer to the Payroll training for further guidance on how to create / update Company Reference Data.

2.4.2. Division

The *Maintain Divisions* screen will open in query mode i.e. this will appear blank:

Division Code	Company Code	Active on Staff Req.	Personnel Inactive
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐

1. Click the  button at the top left of the screen to return all existing Divisions.
2. If no Divisions exist on CoreHR yet, this button must still be clicked in order to update the screen to input mode, so that new records can be entered on screen and saved.

People Management: Configuring the Organisational Structure

Division Code	Division Description	Company Code	Company Description	Active on Staff Req.	Personnel Inactive
1000	SENIOR MANAGEMENT	1000	ABC SOLUTIONS	☒	☐
1001	SHARED SERVICES	1000	ABC SOLUTIONS	☒	☐
1002	SALES & MARKETING	1000	ABC SOLUTIONS	☒	☐
				☐	☐
				☐	☐
				☐	☐
				☐	☐


To add a new Division, update all required fields in the next available blank row. See description of all fields below.

Item	Description	Mandatory
Code	Up to 4 digits only	Yes
Description	Up to 40 alphanumeric characters	Yes
Company Code	Link the Division to an existing Company Code Enter the cursor in the Company Code field and click F9 on the keyboard or  to access the Company list of values.	Yes
Active on Staff Req	Only relevant if using Staff Request in Recruitment.	No
Personnel Inactive	Enabled: The Division is inactive and not available for selection throughout the software on Division lists. Disabled: The Division is active and available for selection throughout the software on Division lists	No

3. Repeat for all Divisions required.
4. Click the  button to save the reference data items.

2.4.3. Management Unit

The *Maintain Management Units* screen will open in 'input mode' i.e. ready to record new items.



The screenshot shows a software window titled "Maintain Management Units". The window has a toolbar with icons for navigation (up, down, left, right arrows), save, delete, add, print, help, and information. Below the toolbar, the window is divided into two main sections. The top section is titled "Maintain Management Units" and contains a table. The table has five columns: "Unit", "Description", "Analysis Code", "Description", and "Active". The table contains several rows of data, with the first row highlighted in blue. The "Unit" column contains codes like FIN, HR, IT, MKT, SALES, and SMGT. The "Description" column contains corresponding department names like FINANCE, HUMAN RESOURCES, IT, MARKETING, SALES, and SENIOR MANAGEMENT. The "Active" column contains checkboxes, all of which are checked.

Unit	Description	Analysis Code	Description	Active
FIN	FINANCE			☒
HR	HUMAN RESOURCES			☒
IT	IT			☒
MKT	MARKETING			☒
SALES	SALES			☒
SMGT	SENIOR MANAGEMENT			☒
				☐
				☐
				☐

To add a new Management Unit:

1. Update all required fields in the next available blank row. See description of all fields below.

Item	Description	Mandatory
Code	Up to 6 alphanumeric characters	Yes
Description	Up to 40 alphanumeric characters	Yes
Analysis Code	Optional setting to group reference data items using an Analysis Code. Enter the cursor in the Analysis Code field and click F9 on the keyboard or  to access the Analysis Code list of values.	No
Active	Enabled: The Management Unit is active and available for selection throughout the software on Management Unit lists. Disabled: The Management Unit is inactive and not available for selection throughout the software on Management Unit lists.	Yes

2. Repeat for all Management Units required.
3. Click the  button to save the reference data items.

2.4.4. Department

The *Maintain Department Codes* screen will open in 'input mode' i.e. ready to record new items.

People Management: Configuring the Organisational Structure

Department Code	Description	Analysis Code	Description	Sensitive Unit	Active
CEO	CEO			☐	☒
FIN1	ACCOUNTS			☐	☒
FIN2	BUDGET			☐	☒
FIN3	TAX			☐	☒
FIN4	FINANCE ADMIN			☐	☒
HR1	RECRUITMENT			☐	☒
HR2	COMPENSATION & BENEFITS			☐	☒
HR3	TRAINING			☐	☒
HR4	PAYROLL			☐	☒
HR5	HR ADMIN			☐	☒
IT1	TECHNICAL SUPPORT			☐	☒
IT2	NETWORKS			☐	☒
IT3	IT SECURITY			☐	☒
M1	LEAD NURTURING			☐	☒

To add a new Department:

1. Update all required fields in the next available blank row. See description of all fields below.

Item	Description	Mandatory
Code	Up to 6 alphanumeric characters	Yes
Description	Up to 40 alphanumeric characters	Yes
Analysis Code	Optional setting to group reference data items using an Analysis Code. Enter the cursor in the Analysis Code field and click F9 on the keyboard or  to access the Analysis Code list of values.	No
Sensitive Unit	If this is enabled, users will require an additional level of access to see employees and posts in this Department. Please Note: This is only available for use in the back-office application for v24. Not available to use in HR Admin.	No
Active	Enabled: The Department is active and available for selection throughout the software on Department lists.	Yes

Disabled: The Department is inactive and not available for selection throughout the software on Department lists.

2. Repeat for all Departments required.
3. Click the  button to save the reference data items.

2.4.5. Work Group

Please note: The Work Group reference data is typically managed as part of Workforce Management Configuration. It is recommended to refer to the Workforce Management training for further guidance on how to create / update Work Group reference data.

2.4.6. Cost Centre

 **Note:** The Cost Centre reference data is typically managed as part of Payroll Configuration. It is recommended to refer to the Payroll training for further detailed guidance on how to create / update Cost Centre reference data.


The *Maintain Cost Centre Codes* screen will open in 'input mode' i.e. ready to record new items.

1. Update all required fields in the next available blank row. See description of all fields below.

Item	Description	Mandatory
Code	Up to 13 alphanumeric characters	Yes
Description	Up to 40 alphanumeric characters	Yes
Activity Code	Optional setting to link the reference data items using an Activity Code.	No

People Management: Configuring the Organisational Structure


Item	Description	Mandatory
	Enter the cursor in the Activity Code field and click F9 on the keyboard or  to access the Analysis Code list of values.	
Active	Enabled: The Cost Centre is active and available for selection throughout the software on Department lists. Disabled: The Cost Centre is inactive and not available for selection throughout the software on Cost Centre lists.	Yes
Link to Hierarchy	Optional feature to allow the user to jump to the Linked Hierarchy definition and add the Cost Centre directly to the Hierarchy. Only relevant if the Cost Centre level has the <i>Hierarchy Indicator</i> flag enabled.	No



 **Note:** This is typically a Payroll field and guidance provided here should be further reviewed in line with the Payroll configuration for an organisation.

2.4.7. Location

The *Location* screen will open in 'input mode' i.e. ready to record new items.



To add a new Location:

1. Update all required fields in the next available blank row. See description of all fields below.

Item	Description	Mandatory
Code	Up to 4 digits only.	Yes
Description	Up to 40 alphanumeric characters.	Yes
Area Code	Optional setting to group Locations items using an Area Code. Enter the cursor in the Area Code field and click F9 on the keyboard or  to access the Area Code list of values.	No
Accum Overseas	Field not applicable.	No
Address	It is possible to define the address associated with each individual location. Up to 5 lines are available per address.	No

2. Repeat for all Locations required.
3. Click the  button to save the reference data items.

Note: There is no 'Active' indicator for Location reference data. All codes listed here will be active and available for selection on Location lists throughout CoreHR.

2.4.8. User Fields 1 – 5

The *User Field 1 – User Field 5* levels are available to enable an organisation to define further levels on their Organisational Structure where more levels are required, outside of the standard 7 levels (i.e. Company, Division, Management Unit, Department, Work Group, Cost Centre, Location).

When a User Field option is added to the Organisational Structure, this will most likely be relabelled. However, when clicking the **Reference** button for one of these items, the screen title will always reflect the User Field # i.e. *Maintain User Field 1 Types*.

The *Maintain User Field # Types* screen will open in 'input mode' i.e. ready to record new items.

User Field	Description	Analysis Code	Description	Active
D1	PAYROLL			☒
D2	HR			☒
D3	CONTRACTS			☒
D4	RECRUITMENT			☒
D5	FINANCE			☒
HIST	HISTORIC			☒
SYST	SYSTEM			☒
				☐
				☐
				☐
				☐
				☐
				☐
				☐

To add a new User Field # item:

1. Update all required fields in the next available blank row. See description of all fields below.

Item	Description	Mandatory
User Field #	i.e. Code. Up to 6 alphanumeric characters	Yes
Description	Up to 40 alphanumeric characters	Yes
Analysis Code	Optional setting to group reference data items using an Analysis Code. Enter the cursor in the Analysis Code field and click F9 on the keyboard or  to access the Analysis Code list of values.	No
Active	Enabled: The User Field is active and available for selection throughout the software on User Field lists. Disabled: The User Field is inactive and not available for selection throughout the software on User Field lists.	Yes

2. Repeat for all User Fields required.
3. Click the  button to save the reference data items.

2.5. Linking the Hierarchy

Linking the hierarchy refers to steps taken to create the actual hierarchical representation of the organisation's structure using:

- The levels flagged with the *Hierarchy Indicator*.
- The active reference data created for those levels.

Essentially, this is the process of expanding this:

Add New Hierarchy Structure

Maintain Hierarchy Structure

Structure Code: ABC ? ABC SOLUTIONS


Description: ABC SOLUTIONS

Available Fields

Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode
ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Description-Code Reference
DIV	Division			☒	☐	Description-Code Reference
MGU	Management Unit			☒	☐	Description-Code Reference
DEPT	Department			☒	☐	Description-Code Reference
COST	Cost Centre			☐	☐	Description Reference
LOC	Location	1	HEAD OFFICE	☐	☒	Description Reference
WRKGRP	Work Group			☐	☐	Description Reference
USER1	User Field1			☐	☐	Description Reference
				☐	☐	Description Reference
				☐	☐	Description Reference
				☐	☐	Description Reference
				☐	☐	Description Reference

Buttons: Save And Close, Save, Cancel, Clear, Activate

into a tree like structure to include all the reference data items for the levels defined e.g.



Before proceeding, confirm that the following configuration has been completed:

- An Organisational Structure exists
- All required levels for the *data tree* are flagged with the *Hierarchy Indicator*
- Active reference data items exist for all required levels
- The Organisational Structure has been activated.

2.5.1. How to access the Hierarchy Maintenance

To access the *Hierarchy Maintenance* screen where the hierarchy is defined:


1. Go to *CorePersonnel > Maintenance > Post Management* and select **Organisational Hierarchy**.

The *Maintain Hierarchy Structure* screen opens.


2. Click the **Data** button for the required structure



Note: If the structure is not activated, this screen will not open (see [2.2.8 Activate the Organisational Structure](#))



The *Hierarchy Maintenance* screen opens:



Section 1

- This is a view only section of the screen that will display the current *Organisational Hierarchy*.

Section 2


- This is a view only section of the screen that will display the list of levels from the Organisational Structure that have the *Hierarchy Indicator* flag enabled.
- The levels will be displayed in the order that they are configured on other Organisational Structure.

Section 3

- This section provides access to a set of buttons that will allow the user to add or remove the items from each level of the hierarchy.
- The buttons displayed will vary, depending on the item selected in the Hierarchy section (Section 1). For example:

People Management: Configuring the Organisational Structure

- In the screenshot above, the top level of the Organisational Structure is selected i.e. the Structure Code = "ABC Solutions", therefore the only button available is **Add Company**.
- In the screenshot below, an element at the third level is selected i.e. a Management Unit of "SMGT – Senior Management", therefore the buttons available are: **Add Management Unit; Add Department; Delete Management Unit**.




At the top of the screen, the *Structure Code* list will only ever include one option i.e. the Structure Code that the Hierarchy is being created for.

The *Search Text* option allows the user to search the configured Hierarchy using a keyword.

- Enter text in the *Search Text* field and click **Find Next**.
- The system will identify Hierarchy Levels that match the search item by highlighting the text in blue.
- Continue to click **Find Next** to identify all matching items in the Hierarchy.


People Management: Configuring the Organisational Structure



2.5.2. Creating a Hierarchy

If creating a hierarchy from scratch on CoreHR, the user will be prompted with the following message when they access this screen for the first time for a new Structure Code:

"No hierarchy data currently exists. Would you like to create level one of this hierarchy?"



Click **Yes** to proceed.

The screen will automatically update to display the Structure Code and org structure levels.

People Management: Configuring the Organisational Structure

The screenshot shows a software window titled "Hierarchy Maintenance...". The window is divided into several sections:

- Top Bar:** Contains a series of navigation icons (back, forward, search, etc.) and a help icon.
- Hierarchy Maintenance Section:**
 - Structure Code:** A dropdown menu currently showing "ABC SOLUTIONS".
 - Search Text:** An empty text input field.
 - Find:** A button to search for a specific entry.
- Hierarchy Section:** A large list box containing a single entry: "ABC SOLUTIONS".
- Hierarchy Configuration Section:**
 - Structure Code:** Displays "ABC SOLUTIONS".
 - Level 1:** Company
 - Level 2:** Division
 - Level 3:** Management Unit
 - Level 4:** Department
- Add Company:** A button located at the bottom right of the window.

This will save automatically.


2.5.3. Add a Company / Initial Level

The first level to be added to the Hierarchy will be the top level as defined in the Organisational Structure. This is typically company.


To add the first level to the Hierarchy:

1. Click on the Structure Code in the Hierarchy window e.g. ABC Solutions below
2. Click on the **Add Company** button on the bottom right of the screen.

The button displays the label for the top level e.g. if the level has been relabelled or if a different element is at the top level.




3. The *Add Company* screen opens:



4. Enable the *Add to Hierarchy* indicator for the required Company / Companies.
 - It is possible to add many records at a time.
 - Use the *Search* box to perform a keyword search on the list of Companies.

5. Click the **Add** button.

The pop-up window closes and the Company (or other level) will be displayed in the Hierarchy section of the screen.




The text displayed for the Level on this screen is dependent on the *Display Mode* set for that level when defining the Organisational Structure (see [2.2.7 Display Mode](#))

6. Select that first level in the Hierarchy section and note that there are now three new buttons available at the bottom right of the screen – in the screenshot above, based on that Organisational Structure, these are:
 - Add Company
 - Add Division
 - Delete Company

2.5.4. Add Levels to the Hierarchy

All levels are added to the Hierarchy in the same way.

1. Select the level in the Hierarchy that you wish to add another element beneath e.g.
in the screenshot below, the *Division* (i.e. Level 2) of "1001 – Shared Services" is selected.



The buttons at the bottom right of the screen update accordingly e.g.

- **Add Division** (i.e. add another element for the current level)
- **Add Management Unit** i.e. (or add an element for the next level down)
- **Delete Division** (i.e. or delete the current element selected at this level.)

The buttons available will differ depending on the level of the Hierarchy element select e.g. if a *Management Unit* was selected in the above screenshot these would display:

- **Add Management Unit**
- **Add Department**
- **Delete Add Management Unit**

2. Click on the required **Add** button and the corresponding *Add* screen will display.

People Management: Configuring the Organisational Structure

- In this example, we will add a new Management Unit beneath the “Shared Services” Division.
3. On the *Add* screen, search for the required item and enable the *Add to Hierarchy* checkbox
- The levels displayed at the top of the screen identify where in the Hierarchy these items will be added beneath i.e. these will be added under “Shared Services” Division.
 - It is possible to select many items on this screen to add at once.
 - If an item has already been added to this branch of the Hierarchy, it will not be listed on this screen e.g. if Finance has already been configured, it would not be listed here

Add Management Unit

Hierarchy Maintenance


Level 1: Company ABC SOLUTIONS - 1000
Level 2: Division SHARED SERVICES - 1001
Level 3: Management Unit -

Include Linked Items ☐

Search

Management Unit	Description	Add To Hierarchy
FIN	FINANCE	☒
HR	HUMAN RESOURCES	☒
IT	IT	☒
MKT	MARKETING	☐
SALES	SALES	☐
		☐
		☐
		☐
		☐
		☐

4. Click the **Add** button to add all selected items




The new items will display on the Hierarchy.

5. Select one of the new items on the Hierarchy, to update the buttons on screen so that the items can be added to the remaining lower levels in that branch of the Hierarchy.

Once the lowest level has been reached i.e. the last level on the Organisational Structure where the *Linked Hierarchy* indicator is enabled, only 2 buttons will be available e.g.

- Department is the lowest level in the example in the screenshot below.
- The Department of "Technical Support" is selected.
- There is no option to add a level beneath this department.
- There is an option to:
 - **Add Department** i.e. add another item at the current level
 - **Delete Department** i.e. delete the selected item from the Hierarchy.

People Management: Configuring the Organisational Structure




5. Repeat the steps above to define all the levels for all branches of the Hierarchy i.e. click on an element in the Hierarchy and use the **Add** buttons to add the items required beneath that level.

Note: All **changes are saved immediately** on this screen i.e. once an item is added or removed, there is no further requirement to save this. Caution is advised if amending an existing Hierarchy that is currently in use, as this can have a direct impact on exiting Post Profile and Post Appointment / Contract records.

2.5.5. Remove a Level


To remove an element from the Hierarchy:

1. Select the item in the Hierarchy e.g. "Shared Services".
2. Click the corresponding **Delete** button at the bottom right of the screen
 - E.g. **Delete Division**
 - The buttons update to display the level of the element select.



3. If there are further elements defined beneath that selected element, the all further sub-elements will be deleted.

A pop-up alert will require you to confirm that you are happy to delete this.



Note: All **changes are saved immediately** on this screen i.e. once an item is added or removed, there is no further requirement to save this. Caution is advised if amending an existing Hierarchy that is currently in use, as this can have a direct impact on exiting Post Profile and Post Appointment / Contract records.

2.5.6. Shared Hierarchy Elements

It is possible to add the same element to multiple branches of the hierarchy. This may be necessary, depending on an organisation's specific requirements.

When adding an element to the Hierarchy, ensure the **Include Linked Items** flag is enabled.

This will ensure that the list of elements displayed on screen will reflect the list of all:

- Elements that have not yet been included in any branch of the hierarchy
- Elements that have been included in other branches of the hierarchy

Add Management Unit

Hierarchy Maintenance

Level 1: Company 1000 - ABC SOLUTIONS
Level 2: Division 1001 - SHARED SERVICES
Level 3: Management Unit -

☒ Include Linked Items

Search Search

Management Unit	Description
MKT	MARKETING
SALES	SALES
SMGT	SENIOR MANAGEMENT

Add To Hierarchy ☐


2.6. Other Configuration Options

2.6.1. Default to Collapse / Expand Hierarchy Display

It is possible to configure the display of the linked hierarchy to be either fully collapsed or fully expanded when the screen is accessed.


This is controlled via the following parameter:

1. Go to *Reference > Reference Q -Z > System Parameters – Advanced*
2. Click the **Client Parameters** button
3. On the *Client Parameters* screen search for the parameter:
“Collapse Hierarchy Tree in PER755”




Enabled:

The hierarchy will be fully collapsed to the highest level i.e. *Structure Code*.



Disabled

All levels of the hierarchy will be fully expanded




2.7. Menu Options

2.7.1. Organisational Hierarchy

To access the Organisational Hierarchy screens, the following Menu Options are required:

Installed System	Menu Option
CorePersonnel	Post Management Menu-Organisational Hierarchy



This menu option will provide access to the *Maintain Hierarchy Structure* screen and all screens within that.

This will not provide access to the reference data screens for the hierarchy levels. Further menu options are required for this and listed in this document.

2.7.2. Company Reference Data

This menu option is required to access the screen used to manage *Company* reference data (see [2.4.1 Company](#)).

Installed System	Menu Option
CorePersonnel	Reference Menu K-P-Maintain Organisations

2.7.3. Management Unit

This menu option is required to access the screen used to manage *Management Unit* reference data (see [2.4.3 Management Unit](#)).

Installed System	Menu Option
CorePersonnel	Reference Menu K-P-Management Units

2.7.4. Department

This menu option is required to access the screen used to manage *Department* reference data (see [2.4.4 Department](#)).

Installed System	Menu Option
CorePersonnel	Reference Menu D-J-Departments

2.7.5. Division

This menu option is required to access the screen used to manage *Division* reference data (see [2.4.2 Division](#)).

Installed System	Menu Option
CorePay	Corporate Menu - Maintain Divisions

2.7.6. Location

This menu option is required to access the screen used to manage *Location* reference data (see [2.4.7 Location](#)).

Installed System	Menu Option
CorePersonnel	Reference Menu K-P-Location_Codes