

Configure Pay Scales

User Guide

PeopleXD

Table of Contents

Document Control	4
1. Overview.....	5
1.1. Purpose of the Guide	5
1.2. What are Pay Scales	5
1.3. Pay Scale Screens	6
1.3.1. People Management.....	6
1.3.1.1. Payroll.....	6
2. Configure Pay Scales	8
2.1. Pay Scales.....	8
2.1.1. Maintain Pay Scales.....	9
2.2. Pay Scale Points.....	10
2.2.1. Maintain Pay Scale Points	11
2.3. Pay Scale Rates.....	11
2.3.1. View Pay Scale Rates	12
2.3.2. Maintain Pay Scale Rates.....	13
3. Pay Scale Restrictions	14
3.1. Overview.....	14
3.1.1. Important Considerations.....	14
3.2. Configure Pay Scale Restrictions.....	14
3.2.1. Edit a Rule.....	15
3.2.2. Deactivate a Rule	16
3.3. Turn on Pay Scale Restrictions	16
4. User Access	17

Table of Contents

4.1.	People Management Menu Options	17
4.2.	Payroll Menu Options	17

Document Control

Version	Date	Author	Details
1.0	27 th Oct 2025	Isabelle Grey	User guide published.

1. Overview

1.1. Purpose of the Guide

The purpose of this guide is to provide detailed guidance on how to configure pay scales in PeopleXD.

This includes:


- An overview of what pay scales are.
- Where pay scales can be configured
- How to configure pay scales
- How to configure a pay scale restriction matrix

1.2. What are Pay Scales

A pay scale/grade/position in conjunction with the scale point defines the amount of pay an employee will receive. These scales are typically categorised based on factors such as job role, experience, length of service, and level of responsibility.

There are three components of a pay scale:

- **Pay Scale** (also known as grade or position) - the pay scale the employee is on.
- **Pay Scale Point** - the points/levels available on the pay scale.
- **Pay Scale Rates** - the rate of pay associated with each scale point.





Note: Employees with personal rates do not need pay scales and scale points. A specific rate of pay is entered on their employee record in People Management for example where positions have no defined salary and can be negotiated.

1.3. Pay Scale Screens

Pay scales can be configured on both the People Management and Payroll Dashboards. Depending on how your organisation is set up this may be the role of the HR or Payroll administrator.

1.3.1. People Management

To configure pay scales in People Management:

1. On the **People Management Dashboard** click the **Data Centre** tab.
2. On the Data Centre widget open the **Reference Data** option.
3. Search for pay scale.

Reference Data

People Management > Reference Data

pay scale Reference Data

Reference Data

Pay Scale Point Pay Scale Rates Pay Scales

1.3.1.1. Payroll

To configure pay scales in Payroll:

1. Go to the **Payroll Dashboard** and click **Settings** tab.
2. Search for and click **Position Reference** to configure pay scales.
3. Search for and click **Scale Point Profile** to configure pay scale points.

Settings

Pay Rates

Position Reference

Scale Point Profile

- Click the **Pay Rates** tab.
- Search for and click **Add Position Rates** to configure pay scale rates.

Pay Rates

Search

View and Add Pay Rate by Code

View Position Rates

View Allowance Scale Rates

Add Position Rates

Add Allowances Rates

 **Note:** There are additional options available in Payroll to maintain pay rates, for example to update in bulk. See [the Pay Rates - User Guide](#) for further details.

2. Configure Pay Scales

Pay scales can be set up and managed in both People Management and Payroll depending on your organisations process.

Note: It is recommended for HR administrators to review additional functionality and complexities with the Payroll team before implementing changes.

2.1. Pay Scales

To configure pay scales:

1. Go to the Pay Scales or Position Reference screen.

Position Code	Description	Nett Pay		Currency	Posn. Group	Allw. Code	Annual Lev 1	Ann Lev
		Minimum	Maximum					
1	System Position Code	0.00	0.00				0.00	
2	Graduate Pay Scale	0.00	0.00				0.00	

2. Click **Add**.
3. Fill in the fields.

Field	Description
Code	Max 6 alphanumeric characters.
Description	Fill in the description.
Nett Pay (Minimum)	Fill in the minimum Nett Pay. This flags employees on this position who fall below this minimum nett pay on the gross to nett exception messages.
Nett Pay (Maximum)	Fill in the maximum Nett Pay. This flags employees on this position who go above this maximum nett pay on the gross to nett exception messages.
Currency	Select the currency code.

Field	Description
Posn Group	Group positions under the same position group code.
Allow Cod	Select an allowance code to be used for that position.
Annual Lev 1	Fill in the annual leave entitlement level 1.
Annual Lev 2	Fill in the annual leave entitlement level 2.
PHI Rate	Bespoke field.
Pos Type	Select a position type.
Rn Dn	Bespoke field.
APTH Code	Government sector related
Part Time	Identify the position as a part time position.
Min Rate Exclude	Select to exclude from the minimum rate check.
Occupation Status Code	Used in Conjunction with the CSO Module. This is a code used for mapping the position to one of the CSO categories.
CSO Contracted Hours	Used in Conjunction with the CSO Module. Records the default position hours which the CSO Module will use, if parameter selected, for the hours worked in the CSO return.
ESS Timesheet	Select to make available when recording ESS Timesheets in portal.
ESS Quantity	Select if quantities are required when recording ESS Timesheets in portal.
ESS Fixed Quantity	Select if fixed quantities are required when recording ESS Timesheets in portal.
Active on Staff Req	Turn on to include in the Pay Scale drop-down lists on Staff Requests within Recruitment.
S&S Alleviation	Bespoke field.
Roll up Multiplier	Fill in the roll up multiplier.
Overtime Hours	Fill in overtime hours.

4. Click **Save**.

2.1.1. Maintain Pay Scales

You can maintain pay scales by updating or amending the fields. Please note:

- Changes made update immediately on the system and are visible for all records.

- Pay scales that have been used or attached to an employee record can't be deleted as the system needs to hold a record of how an employees pay was calculated and it refers to these scales when calculating behind the scenes e.g. for arrears.

2.2. Pay Scale Points

To configure pay scales:

- Go to the Pay Scale Point or Scale Point Profile screen.
- Select a **Position Code** from the drop-down list.

Pay Scale Point
People Management > Reference Data > Pay Scale Point

Scale Point Profile

Position Code
Graduate Pay Scale

Scale Point	Scale Narrative	Scale Desc.	Bar Point	Age	Ind.	Progression		Years On Point	L.S.I. Ind	APTH Start Pt.	
						Scale	Point				
1	Point 1							1	Y		...
2	Point 2							1	Y		...
3	Point 3							2	Y		...

Cancel
Add
Save

- Click **Add**.
- Fill in the fields.

Field	Description
Position Code	Select the Position Code/Pay Scale you want to add scale points to.
Code	Max 4 numeric characters.
Scale Narrative	Fill in the narrative this is displayed in reference data lists.
Scale Desc	Max 5 alphanumeric characters.
Bar Point	Select if this is a barrier point. This means the person doesn't increment beyond this point automatically and requires user instruction to say employee should be incremented beyond this.

Field	Description
Age	If using age-based increments fill in the age the increment is given.
Ind	Enter Y to use age-based increment.
Progression Scale	If using increments/progression select a scale. This can be the same scale as the previous progression or a different scale.
Progression Point	If using increments/progression select a point. This is the point the employee will move to on the selected scale.
Years on Point	If using length of service increments fill in the number of years an employee must be on this scale point before the increment is given.
L.S.I. Ind	Enter Y to use years on point based increment.
APTH Start Pt	Government Department Specific

5. Repeat for all required scale points.
6. Click **Save**.

2.2.1. Maintain Pay Scale Points

You can maintain pay scale points by updating or amending the fields. Please note:

- Changes made update immediately on the system and are visible for all records.
- Pay scales can be deleted using the option from the 3-dot menu.

2.3. Pay Scale Rates

Pay scale rates are typically set up and maintained on the Payroll Dashboard.

To configure pay scale rates:

1. Go to the **Add Position Rates** screen.

2. Select a **Position Code** from the drop-down list.
3. Fill in the **Rate Sequence Number**.

Note:

The Rate Sequence field is always populated with a value of 1.

4. Select the **Effective Date**.
5. Fill in a unique **Reference**.
6. Click **Add** and fill in the fields.

Field	Description
Scale Point	Fill in a valid scale point code.
Hourly Rate	Fill in the rate. It is only possible to record 1 rate per point e.g. Hourly OR Daily OR Annual OR Weekly OR Unit
Daily Rate	
Annual Salary	
Weekly Rate	
Unit Rate	

7. Click **Add** and repeat the steps above to add all the required rates.
8. Click **Save**.

Note: Pay rates cannot be edited or deleted once saved.

2.3.1. View Pay Scale Rates

To view position rates:

1. Go to the **View Position Rates** screen.
2. Select the **Position** from the drop-down menu.
3. Select the **Date Effective** from the drop-down menu.

Rate Seq No	Date Input	Reference	Scale Point	Hourly Rate	Daily Rate	Annual Salary	Weekly Basic	Unit Rate
1	22-MAR-22	1	1	0	0	20000	0	0
1	22-MAR-22	2	2	0	0	22000	0	0
1	22-MAR-22	3	3	0	0	24000	0	0

2.3.2. Maintain Pay Scale Rates

Pay rates cannot be edited or deleted, this ensures there's a record of previous rates on the system. To make changes to a rate made in error you can add new position rates with the same effective date and a different reference.

3. Pay Scale Restrictions

3.1. Overview

A matrix of rules can be configured to identify the Pay Scales that are applicable to specific employee attributes e.g. Country, Division, Employment Status etc. This means when a HR administrator is creating the salary for an employee, they can only select from the Pay Scales that match those rules.

For example, if the Pay Scales “Grade 1” and “Grade 2” should only apply to UK based employees, then HR administrators only see those Pay Scales when the employee’s address is based in the UK.

Care needs to be taken when defining the matrix of rules to ensure that all employee scenarios are catered for because if an employee does not match any rule, no Pay Scale will be available.

3.1.1. Important Considerations

All employee scenarios need to be catered for to ensure that there is always a Pay Scale available to select for the employee’s salary on screen.

For example, if you create a rule allocating pay scales to UK employees and no other rules exist. If an employee’s address is anywhere other than ‘United Kingdom, no Pay Scales will be available to select for their salary.

Therefore, great care must be taken when setting up the matrix to ensure that all scenarios are catered for.

3.2. Configure Pay Scale Restrictions

To create pay scale restrictions:

1. On the **People Management Dashboard** click the **Data Centre** tab.
2. On the Data Centre widget open **HR Admin Settings Setup**.
3. Click **Payscale Restrictions**.

Configure Pay Scales - User Guide

Payscale Restrictions

People Management > HR Admin Setup Settings > Payscale Restrictions

Search

ADD NEW

Reference Type	Reference Attribute	Reference Type	Reference Attribute	Payscales	Active
NOTHING TO SEE HERE EXCEPT THIS FLAG					

0 - 0 of 0

access PeopleXD

UPDATE

4. Click **Add New**.

Payscale Restriction Setup

People Management > HR Admin Setup Settings > Payscale Restrictions > Payscale Restriction Setup

Select Reference Type 1 *

Select Reference Item *

Select Reference Type 2

Select Reference Item

Available

Enter Search Text

☐ Graduate Pay Scale

☐ System Position Code

Assigned

Enter Search Text

SAVE

access PeopleXD

5. Select a **Reference Type** e.g. Country.
6. Select a **Reference Item** e.g. United Kingdom.
7. Select a second Reference Type and Item if required.
8. Select the required pay scale(s) from the Available list and click the **Arrow Icon** to move it to the Assigned list.
9. Click **Save**.

3.2.1. Edit a Rule

To edit a pay scale restriction rule:

1. Go to the **Payscale Restrictions** screen.
2. Expand the rule's **three-dot menu** and click **Edit**.
3. Update the rule as required e.g. to add or remove pay scales.
4. Click **Save**.

3.2.2. Deactivate a Rule

To activate or deactivate a pay scale restriction rule:

1. Go to the **Payscale Restrictions** screen.
2. Turn the **Active** toggle on/off.
3. Click **Update**.


3.3. Turn on Pay Scale Restrictions

Pay scale restrictions are controlled by a parameter. This means that once the matrix of rules has been defined, the parameter needs to be turned on to apply restrictions. This ensures restrictions only apply once you've completed the setup of the matrix.

 **Note:** This is a global setting and once the parameter is enabled this impacts all users when they are creating and amending salary records.

To enable the parameter:

1. Navigate to the **Site Manager** widget and Open **Admin Settings**.
2. Search for the parameter 'cp_rest_pay_scale_matrix'



Admin Settings			
Administrator Dashboard > Admin Settings			
Coreportal Parameters			
cp_rest_pay_scale_matrix Search Whole Phrase			
Parameter Description	Parameter Code	Product Name	Current Value
Restrict HR Admin Payscale by Matrix	cp_rest_pay_scale_matrix		N EDIT

3. Click **Edit**.
4. Update the Value to **Y**.
5. Click **Save**.

4. User Access

4.1. People Management Menu Options

The following menu options are required to access the payroll reference data screens from the Data Centre.

Menu Option	Menu ID	System
REFERENCE DATA	MAIN_MENU.REFERENCE_DATA	People Management
REFERENCE DATA MENU - PAY REFERENCE DATA	REFERENCE_DATA_MENU.PAY_REFERENCE	People Management
Create bytype	WS_REFDATA_MENU.POST_BYTYPE	Web Service
Get bytype	WS_REFDATA_MENU.GET_BYTYPE_TYPE	Web Service
Get types	WS_REFDATA_MENU.GET_TYPES	Web Service
Update by type	WS_REFDATA_MENU.PATCH_BYTYPE	Web Service

The following menu options are required to access the pay scale restriction screens from the Data Centre.

Menu Option	Menu ID	System
SETTINGS AND SETUP MENU - ORGANISATIONAL CONFIGURATION	SETTINGS_SETUP_MENU.ORGANISATIONAL_CONFIGURATION	People Management
PAYSCALE RESTRICTION MATRIX	ORGANISATIONAL_CONFIGURATION_MENU.PAYSCALE_RESTRICTION_MATRIX	People Management

4.2. Payroll Menu Options

The following menu options are required to access the pay scale screens

Menu Option	Menu ID	System
MAIN MENU - Settings	MAIN_MENU.SETTINGS	CorePorta I Pay
Settings - Position Reference	SETTINGS_MENU.POSITIONREFERENCE	CorePorta I Pay
Settings - Scale Point Profile	SETTINGS_MENU.SCALEPOINTPROFILE	CorePorta I Pay
Main Menu - Payrates	MAIN_MENU.PAYRATES	CorePorta I Pay
Payrates - View and Add Pay Rate by Code - Add Position Rates	PAYRATES_MENU.VIEWANDADDPAYRATE.ADDPOSITIONRATES	CorePorta I Pay
Payrates - View and Add Pay Rate by Code - View Position Rates	PAYRATES_MENU.VIEWANDADDPAYRATE.VIEWPOSITIONRATES	CorePorta I Pay
Create settings positionref	WS_PAYROLL_MENU.POST_SETTINGS_POSITIONREF	Web Services
Delete settings positionreference	WS_PAYROLL_MENU.DELETE_SETTINGS_POSITIONREFERENCE_ID	Web Services
Get settings positionreference	WS_PAYROLL_MENU.GET_SETTINGS_POSITIONREFERENCE	Web Services
Update settings positionref	WS_PAYROLL_MENU.PATCH_SETTINGS_POSITIONREF_ID	Web Services
Get settings scalepointprofile	WS_PAYROLL_MENU.GET_SETTINGS_SCALEPOINTPROFILE	Web Services

Menu Option	Menu ID	System
Update settings scalepointprofile	WS_PAYROLL_MENU.PATCH_SETTINGS_SCALEPOINTPROFILE_ID	Web Services
Create settings scalepointprofile	WS_PAYROLL_MENU.POST_SETTINGS_SCALEPOINTPROFILE	Web Services
Delete settings scalepointprofile	WS_PAYROLL_MENU.DELETE_SETTINGS_SCALEPOINTPROFILE_ID	Web Services
Create payrates positionrates	WS_PAYROLL_MENU.POST_PAYRATES_POSITIONRATES	Web Services
Get payrates positionrates	WS_PAYROLL_MENU.GET_PAYRATES_POSITIONRATES	Web Services