

Personnel Number Generation

User Guide

Access Limited Distribution

People Management

Table of Contents

Document Control	3
1. Overview	4
1.1. Purpose of the Guide.....	4
1.2. Personnel Number Generation Options.....	4
2. How to Configure	5
2.1. Where to access Personnel Number Configuration	5
2.2. Automatic Generation	7
2.2.1. Define the Rule	7
2.2.2. Make Rule Active.....	8
2.2.3. Set the System Parameter to Automatic	9
2.2.4. Create New Employee Wizard	10
2.3. Manual Generation	11
2.3.1. Define the Rule	11
2.3.2. Make Rule Active.....	11
2.3.3. Set the System Parameter to Manual	12
2.3.4. Create New Employee Wizard	13
2.4. Additional Considerations	14
2.4.1. Valid Format Indicator	14
2.4.2. <i>Modulus</i> Generation Routines	14
3. Additional Configuration Required	15
3.1. Menu Options	15

Document Control

Version	Date	Author	Details
1.0	16th Dec 2019	Peter Travers	Published to Access LMS

1. Overview

1.1. Purpose of the Guide

The purpose of this document is to provide guidance on how to configure CoreHR to manage the creation or input of employee numbers on employee setup.

This includes:

- How to define automatic number generation rules.
- How to select either automatic number generation or manual number entry for new hires.
- Where the number is manually entered for new hires.
- Menu options required to access the rule configuration for the personnel number settings.

1.2. Personnel Number Generation Options

In People Management, there are 2 options available to support the creation or input of employee numbers on CoreHR:

1. Default Automatic

- A personnel number is automatically generated for each new hire on CoreHR.
- The number can be generated to match an organisation's employee number format requirements, including prefix, suffix and length.

2. Default Manual

- A personnel number must be manually entered on the system for any new hires setup on CoreHR.
- There is no validation of format supplied.


It is possible to configure the system to use either the automated or manual option. If both options are active, the user will be able to select the required option to use when creating a new employee.

2. How to Configure

2.1. Where to access Personnel Number Configuration

To access the configuration settings for Personnel Numbers:

1. Quick jump to the *Data Centre* widget and **Open** *HR Admin Setup Settings*.
2. Search for *Personnel Numbering Maintenance* and click on the corresponding option under *HR Settings*.



The *Personnel Numbering Maintenance* screen opens.

Personnel Numbering Maintenance

People Management > HR Admin Setup Settings > [Personnel Numbering Maintenance](#)

Personnel Numbering Maintenance

Personnel No Type	Generation Type	Generation Routine	Active	Valid Format	Prefix	Length	Start
Default Automatic	Automatic	Default	☒	☐		6	
Default Manual	Manual	Default	☒	☐			

Cancel

AddSave

There are 2 rows on this screen by default:

- *Default Automatic*: the default rule for **automated** number generation.
- *Default Manual*: the default rule for **manual** number entry.

2.2. Automatic Generation

2.2.1. Define the Rule

The *Default Automatic* rule can be amended if required, to cater for an organisation's specific personnel number format requirements.

Note: The settings on the left-hand side of the screen should not be altered i.e.

Personnel Numbering Maintenance		
Personnel No Type	Generation Type	Generation Routine
Default Automatic	Automatic	Default
Default Manual	Manual	Default

The settings on the right-hand side of the screen may be used to update the format on the personnel number that is automatically created for a new hire.


Personnel Numbering Maintenance									
Generation Routine	Active	Valid Format	Prefix	Length	Start Range	End Range	Last Number	Suffix	
Default	☒	☐		6	0	999999	136		...
Default	☒	☐							...

Option	Description
Prefix	Text that should appear as a prefix to any personnel number generated on CoreHR. It is possible to define up to 4 alphanumeric characters here.
Length	This is the length of the number that will be automatically generated per employee. It is the section of the personnel number that will appear in between the prefix and suffix. e.g. if set to 6 the first number will be 000001.

Option	Description
Start Range	The first number that can be generated on CoreHR.
End Range	The max number that can be generated.
Last Number	The last number to be generated by CoreHR using this rule. E.g. if this displays 136 as above, this would be for a personnel number of 000136. This indicates the next number to be generated i.e. this will be 000137. This can be manually overridden, to force the system to generate a new number e.g. overwriting this to 140 will ensure that next number generated is 000141.
Suffix	Text that should appear as a suffix to any personnel number generated on CoreHR. It is possible to define up to 4 alphanumeric characters here.

The total character count for any personnel number created on CoreHR is **10**.

- This includes prefix, length and suffix.
- There is validation to prevent a rule from being saved if it will result in a total number greater than 10 characters.



2.2.2. Make Rule Active

The rule must be active on the *Personnel Numbering Maintenance* screen.


Personnel Numbering Maintenance									
Generation Routine	Active	Valid Format	Prefix	Length	Start Range	End Range	Last Number	Suffix	
Default	☒	☐		6	0	999999	136		...
Default	☒	☐							...

1. Ensure the *Active* checkbox is selected.
2. Click the **Save** button to save the changes.

2.2.3. Set the System Parameter to Automatic


To set the system to use the automated rule:

1. Quick jump to the *Data Centre* widget and **Open** *HR Admin Setup Settings*.
2. Search for *System Parameters* and click on the corresponding option under *HR Settings*.



The *System Parameters* screen opens.

3. Ensure that *Default Generate Personnel No Routine* is set to *Default Automatic*.



4. Click the **Save** button to save the changes.

Note: This setting ensures that the system will default to use this option. However, it will still be possible for the user to select another active Personnel Number type using the *Personnel Number Routine* field on the *Create New Employee* wizard.

2.2.4. Create New Employee Wizard

When using the automated option, the employee's personnel number is automatically calculated as part of the New Hire setup. The *Personnel Number Routine* field will be defaulted to the *Default Automatic* option, based on the settings applied in [2.2.3 Set the System Parameter to Automatic](#).

However, it is generated on completion of the *Create New Employee* wizard. Therefore, the actual number it is not displayed on the *Person Info* screen of the wizard.

The *Personnel Number Routine* field will allow the user to select from a list of active Personnel Number Routines, if multiple rules exist.

The screenshot shows the 'Create New Employee Wizard' interface. On the left is a sidebar with four steps: 1. Person Information (selected), 2. Organizational Structure, 3. Contract Information, and 4. Salary Information. The main area is titled 'Person Details' and contains several form fields. A red rectangle highlights the 'Personnel Number Routine' dropdown menu, which currently shows 'Default Automatic'. Below this, there are fields for Title, Forename*, Surname*, Middle Name, Known As, Initials, Date Of Birth* (with a calendar icon), Age, Retirement Date (with a calendar icon), Gender*, and Nationality. A section titled 'Contact Details' follows, with fields for Email, Phone, Mobile, and Country*. The 'corehr' logo is visible at the bottom right of the form area.

2.3. Manual Generation

2.3.1. Define the Rule

The *Default Manual* rule should not require any amendments.

Note: The settings on the left-hand side of the screen should not be altered i.e.

Personnel Numbering Maintenance		
Personnel No Type	Generation Type	Generation Routine
Default Automatic	Automatic	Default
Default Manual	Manual	Default

There is no option to apply format validation to the format for numbers entered on the *Create New Employee* wizard.

2.3.2. Make Rule Active

The rule should be active on the *Personnel Numbering Maintenance* screen to ensure that it is available to select on the *Create New Employee* wizard and the [System Parameter](#) screen.


Personnel Numbering Maintenance									
Generation Routine	Active	Valid Format	Prefix	Length	Start Range	End Range	Last Number	Suffix	
Default	☒	☐		6	0	999999	136		...
Default	☒	☐							...

1. Ensure the *Active* checkbox is selected.
2. Click the **Save** button to save the changes.

2.3.3. Set the System Parameter to Manual

To set the system to use the manual rule:

1. Quick jump to the *Data Centre* widget and **Open** *HR Admin Setup Settings*.
2. Search for *System Parameters* and click on the corresponding option under *HR Settings*.



The *System Parameters* screen opens.

3. Ensure that *Default Generate Personnel No Routine* is set to *Default Manual*.

The screenshot shows the 'System Parameters' screen. It has a title 'System Parameters' at the top. Below it is a section titled 'Personnel'. Inside this section, there's a dropdown menu labeled 'Default Generate Personnel No Routine' which is set to 'Default Manual'. This dropdown is highlighted with a red rectangular box. Other fields in the 'Personnel' section include 'Service Days' (set to 5), 'Document Drive', 'Service Break Days' (set to 10), 'Highest Personnel No Prefix', 'Default Retirement Age' (set to 65), 'Default Gender' (set to 'Choose'), and 'FTE Weeks per Year' (set to 52.1400).

4. Click the **Save** button to save the changes.

2.3.4. Create New Employee Wizard

When using the manual option, the employee's personnel number must be manually entered as part of the New Hire setup.

- The *Personnel No* field is available at the top of the screen for the *Personal Information* step and is mandatory. This will display only when the *Personnel Number Routine* = *Default Manual*.
- The field allows for the input of up to 10 alphanumeric characters.
- There is no validation applied for numbers that are manually entered.

The screenshot shows the 'Person Details' section of the 'Create New Employee Wizard'. On the left, a sidebar lists four steps: 1. Person Information (selected), 2. Organizational Structure, 3. Contract Information, and 4. Salary Information. The main content area is titled 'Person Details' and contains the following fields:

- Personnel Number Routine:** A dropdown menu currently set to 'Default Manual', which is highlighted with a red rectangular box.
- Personnel No.*:** A text input field for the personnel number.
- Title:** A dropdown menu.
- Forename*:** A text input field.
- Surname*:** A text input field.
- Middle Name:** A text input field.
- Known As:** A text input field.
- Initials:** A text input field.
- Date Of Birth*:** A date picker field.
- Age:** A text input field.
- Retirement Date:** A date picker field.
- Gender*:** A dropdown menu.
- Nationality:** A dropdown menu.

2.4. Additional Considerations

2.4.1. Valid Format Indicator

The *Valid Format* indicator is not applicable for rules used on People Management v27.

Personnel Numbering Maintenance							
Personnel No Type	Generation Type	Generation Routine	Active	Valid Format	Prefix	Length	Start
Default Automatic	Automatic	Default				6	
Default Manual	Manual	Default					

2.4.2. Modulus Generation Routines

There are several *modulus* options on the Generation Routine drop down list on the *Personnel Numbering Maintenance* screen. These are not for general use. These are entirely bespoke and customised for use by specific organisations.

Personnel Numbering Maintenance							
Personnel No Type	Generation Type	Generation Routine	Active	Valid Format	Prefix	Length	Start
Default Automatic	Automatic	Default				6	
Default Manual	Manual	Default					

3. Additional Configuration Required

3.1. Menu Options

The following menu options are required to access screens used as part of the Personnel Number configuration.

System	Menu Option
People Management	Personnel Numbering Maintenance
People Management	System Parameters