



Configuring the Organisational Structure

User Guide

CoreHR Limited Distribution

V28

People Management

Table of Contents

Document Control	4
1. Overview	5
1.1. Purpose of the Guide	5
2. How to Configure	6
2.1. Where to access the Organisational Structure	6
2.2. Add a New Organisational Structure	8
2.2.1. Create the Structure	8
2.2.2. Add Levels to the Structure.....	10
2.2.3. Define Reference Data Items.....	11
2.2.4. Hierarchy Indicator.....	12
2.2.5. Initial Value	14
2.2.6. Hide Indicator	16
2.2.7. Display Mode.....	18
2.2.8. Activate the Organisational Structure.....	19
2.3. Edit an Existing Organisational Structure.....	20
2.3.1. How to Add a Level.....	21
2.3.2. How to Remove a Level.....	22
2.3.3. How to reorder a level.....	24
2.4. Organisational Structure Reference Data.....	25
2.4.1. Company	26
2.4.2. Division.....	26
2.4.3. Management Unit	27
2.4.4. Department.....	28
2.4.5. Work Group	29
2.4.6. Cost Centre	29
2.4.7. Location	31
2.4.8. User Fields 1 – 5.....	31
2.5. Linking the Hierarchy.....	33
2.5.1. How to access the Hierarchy Maintenance	34
2.5.2. Creating a Hierarchy	37
2.5.3. Add a Company / Initial Level	38

Table of Contents

2.5.4. Add Levels to the Hierarchy	40
2.5.5. Remove a Level.....	43
2.5.6. Shared Hierarchy Elements	44
2.6. Other Configuration Options.....	45
2.6.1. Default to Collapse / Expand Hierarchy Display	45
2.7. Menu Options	46
2.7.1. Organisational Hierarchy	46
2.7.2. Company Reference Data	47
2.7.3. Management Unit	47
2.7.4. Department.....	47
2.7.5. Division	47
2.7.6. Location	47
2.8. Auto-Fill Hierarchy	47
2.8.1. Configuring Auto-Fill Hierarchy	48
2.8.2. Auto-Filled Staff Request Wizard	52
2.8.3. Auto-Filled Post Profile Wizard	53
2.8.4. Auto-Filled Contract Wizard	54
2.8.5. Auto-Filled New Contract Wizard	54

Document Control

Version	Date	Author	Details
1.0	16 th Dec 2019	Peter Travers	Published to CoreHR University
2.0	25 th September 2020	Peter Travers	Published to People XD University Added in section on Auto-Fill Hierarchy functionality

1. Overview

1.1. Purpose of the Guide

The purpose of this guide is to provide detailed guidance on how to manage the Organisational Structure & Organisational Hierarchy configuration on CoreHR.

This includes:


- Creating a new Organisational Structure.
- Editing an existing Organisational Structure.
- Creating or updating the reference data that is used specifically by the Organisational Structure.
- Creating or updating the linked Organisational Hierarchy.

2. How to Configure


2.1. Where to access the Organisational Structure

The Organisational Structure is managed in the CoreHR back-office application. To access this:

Go to *CorePersonnel* > *Maintenance* > *Post Management* and select **Organisational Hierarchy**.



The *Maintain Hierarchy Structure* screen opens.



- All existing Organisational Structures are listed on screen.
- For a new implementation, there will always be 1 record here at a minimum i.e. the default Organisational Structure.

The *Structure Code* filter at the top of the screen provides the ability to restrict the records shown on screen to the chosen *Structure Code*. This is set to “All” by default.

From this screen, it is possible to:

- View an existing Org Structure and the corresponding linked hierarchy.
- Edit an existing Org Structure and the corresponding linked hierarchy.
- Access reference data maintenance screens for Org Structure levels.
- Create a new Org Structure and the corresponding linked hierarchy.

2.2. Add a New Organisational Structure

2.2.1. Create the Structure

To add a new *Organisational Structure*:

1. Go to *CorePersonnel > Maintenance > Post Management* and select **Organisational Hierarchy**.

The *Maintain Hierarchy Structure* screen opens.

2. Click the **Add New Structure Code** button.

CorePersonnel - 24.0.6

AC... E... BL... Field Rec... Qu... H... To... Wind...

Maintain Hierarchy Str...

Maintain Hierarchy Structure

Structure Code: All

Add New Structure Code

Add New Structure

Hierarchy

Structure Code	Hierarchy Name	Effective Date	Date Applied	Edit	View	Data	
1	CUSTOMER GROUP NAME	CoreHR	09-AUG-2008	17-SEP-2012	Edit	View	Data
				Edit	View	Data	
				Edit	View	Data	
				Edit	View	Data	
				Edit	View	Data	
				Edit	View	Data	

3. The *Maintain Hierarchy Structure Code* opens. Any existing *Structure Codes* will be displayed here.

To add a new *Structure Code*.


- a. Provide a *Code* (up to 6 alphanumeric characters).
- b. Provide a *Description* (up to 40 alphanumeric characters).
- c. Click the button to save changes.

Maintain Hierarchy Structure...


Maintain Hierarchy Structure Codes

Structure Code	Description	Analysis Code	Description
1	CUSTOMER GROUP NAME		
ABC	ABC SOLUTIONS		

- d. Click the  to close the window.
- e. Back on the *Maintain Hierarchy Structure* click the **Add New Structure** button.



- f. The *Add New Hierarchy Structure* screen will pop up.
- g. Select a *Structure Code*, by clicking the  button for to access the list of all available *Structure Codes*.
The code just created should be available here.
This list will displays active Structure Codes that have not been linked to any other Organisational Structures on the system.



- h. Add a *Description*.
Maximum of 30 alphanumeric characters.
- i. Click the **Save** button.

2.2.2. Add Levels to the Structure

The following levels are mandatory on CoreHR and must be included on all Organisational Structures that are defined on the system:

- Company
- Management Unit
- Department
- Cost Centre
- Location
- Work Group

All other available fields are optional i.e.

- Division
- User Field 1 – User field 5

The Organisational Structure levels may be configured to include any levels (all mandatory levels must be included) in any order, based on an organisation's individual requirements.

To add a level:

1. Click on the level in the Available Fields list at the left of the screen. The level will be highlighted in blue, as per the screenshot below.

Available Fields	Org Structure	Label	Initial Value	Description
Company				
Division				
Management Unit				
Department				
Cost Centre				
Location				

2. Click on the first yellow box for the required row i.e. the box highlighted in the screenshot below. The Org Structure and Label field will update to display the selected level.

Available Fields	Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode
Company	ORGZ	Company					Description Reference
Division							Description Reference
Management Unit							Description Reference
Department							Description Reference

3. Repeat as required for all levels, ensuring all mandatory levels have been included.

Add New Hierarchy Structure
Maintain Hierarchy Structure

Structure Code: ?

Description:

Available Fields	Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode	Reference
Company	ORGZ	Company			☐	☐	Description	Reference
Division	DIV	Division			☐	☐	Description	Reference
Management Unit	MGU	Management Unit			☐	☐	Description	Reference
Department	DEPT	Department			☐	☐	Description	Reference
Cost Centre	COST	Cost Centre			☐	☐	Description	Reference
Location	LOC	Location			☐	☐	Description	Reference
Work Group	WRKGRP	Work Group			☐	☐	Description	Reference
User Field 1					☐	☐	Description	Reference
User Field 2					☐	☐	Description	Reference
User Field 3					☐	☐	Description	Reference
User Field 4					☐	☐	Description	Reference
User Field 5					☐	☐	Description	Reference

Buttons: Save And Close, Save, Cancel, Clear, Activate

4. It is possible to update the label for some of these levels, if required. This may be useful to ensure that the levels displayed to the user on screen are meaningful and reflect an organisation's terminology, when managing Post Profiles and Contracts e.g. to change the text from *Company* to *Legal Entity*.
 - This is possible for most levels that are defined.
 - The following levels cannot be relabelled:
 - Department
 - Cost Centre
 - Work Group
 - Up to 20 alphanumeric characters may be used.
5. Click on the **Save** button at the end of the screen.

2.2.3. Define Reference Data Items

Ensure that all required Reference Data items have been defined. These will be required to:

- Create the linked hierarchy levels.
- Set an initial value.

See [2.4 Organisational Structure Reference Data](#) for further details on how to create and maintain Organisational Structure Reference Data items.


2.2.4. Hierarchy Indicator

The *Hierarchy Indicator* must be enabled for all the levels that will be linked together to form the linked Organisational Hierarchy.

For example, in the screenshot below, the first four levels have the *Hierarchy Indicator* enabled i.e. Company, Division, Management Unit and Department.

Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode
ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Code-Description Reference
DIV	Division			☒	☐	Code-Description Reference
MGTU	Management Unit			☒	☐	Code-Description Reference
DEPT	Department			☒	☐	Code-Description Reference
COST	Cost Centre			☐	☐	Description Reference
LOC	Location			☐	☐	Description Reference
WRKGRP	Work Group			☐	☐	Description Reference
User Field 1				☐	☐	Description Reference
User Field 2				☐	☐	Description Reference
User Field 3				☐	☐	Description Reference
User Field 4				☐	☐	Description Reference
User Field 5				☐	☐	Description Reference

This allows the user to create a linked hierarchy between all these levels i.e.



The indicator will make those levels and all the corresponding Reference Data items that are created for each level, available when defining the linked hierarchy i.e. [\(2.5 Linking the Hierarchy\)](#).

- If the level isn't flagged here with the *Hierarchy Indicator*, it will not be available to link in the hierarchy. For the above screenshot, note that Cost Centre, Location and Work Group are not flagged.
- Levels will be linked in the order displayed on screen i.e. Company *then* Division *then* Management Unit *then* Department. Ensure that the levels have been added in the correct order.

Ultimately, any level that is flagged here, will be displayed on the *Org Structure* step of an employee's contract on People Management, as per screenshot below.

- There will be a defined relationship created on CoreHR for each of these levels (see [2.5 Linking the Hierarchy](#)).
- E.g. If I select Division = *Shared Services*, I will only be able to see Management Units that are in that Division such as *Human Resources* or *IT*.

← Brian Clifford (000112)

New Appointment

People Management > Employee Search > Brian Clifford (000112) > New Appointment

POST SEARCH

1 Organizational Structure

2 Contract Information

3 Salary Information

Post
502201 - Training Manager

Company *
Abc Solutions

Division *
Shared Services

Management Unit *
Human Resources

Department *
HR3 - Training

Cost Centre
Cost Centre*

Location
Location*

Work Group
Work Group*

corehr
Simpler HR Technology

NEXT

2.2.5. Initial Value

The *Initial Value* field provides the ability to set a default value for a level that is always populated on a Post Profile record.

The screenshot shows the 'Add New Hierarchy Structure' dialog box. The 'Structure Code' is 'ABC' and the 'Description' is 'ABC SOLUTIONS'. The 'Available Fields' list on the left includes Company, Division, Management Unit, Department, Cost Centre, Location, Work Group, and five User Fields. The main table lists these fields with their corresponding labels, initial values, and descriptions. The 'Company' row is highlighted, and its 'Initial Value' field is set to '1000' and its 'Description' is 'ABC SOLUTIONS'. The 'Hierarchy Indicator' is checked for the Company, Division, Management Unit, and Department levels. The 'Display Mode' is set to 'Code-Description' for the first four levels and 'Description' for the remaining levels. The 'Reference' column shows a reference icon for each level. The 'Save And Close', 'Save', 'Cancel', 'Clear', and 'Activate' buttons are at the bottom.

Available Fields	Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode	Reference
Company	ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Code-Description	
Division	DIV	Division			☒	☐	Code-Description	
Management Unit	MGTU	Management Unit			☒	☐	Code-Description	
Department	DEPT	Department			☒	☐	Code-Description	
Cost Centre	COST	Cost Centre			☐	☐	Description	
Location	LOC	Location			☐	☐	Description	
Work Group	WRKGRP	Work Group			☐	☐	Description	
User Field 1					☐	☐	Description	
User Field 2					☐	☐	Description	
User Field 3					☐	☐	Description	
User Field 4					☐	☐	Description	
User Field 5					☐	☐	Description	

For example, if the *Company* is always “1000 – ABC Solutions”, then setting this as an *Initial Value* will ensure that is defaulted on all Post Profiles created against this Organisational Structure.

Post Profile Maintenance
People Management > View All > Post Profile Maintenance > [Post Profile Maintenance](#)

Post Profile

Post Title CTO	Post Name Chief Technology Officer	Post Number 502198
Effective Date 01-Jan-1990	Post Profile Type Permanent	Managers Order
Structure Code Abc Solutions	Auto Authorisation ☒	Auto Commencement ☐

Hierarchy Definition

Company 1000	Abc Solutions
Division 1000	Senior Management
Management Unit SMGT	Senior Management

corehr
Smarter HR Technology

- The *Initial Value* can be set for any level included in the Organisational Structure.
- Reference Data items need to be configured for the level, for these to be available to select.

To set an *Initial Value*:

1. For the required level, click the  button next to the *Initial Value*.
2. Select the required reference data item from the list available.
3. Click **OK**.
The reference data item will be displayed on the Organisational Structure screen.
4. Click the **Save** button to save.

2.2.6. Hide Indicator

The *Hide Indicator* may be used to hide a level from the user on the post profile and contract screens on CoreHR.

This is typically used where a level is mandatory on the system, but it is not required for an organisation's definition of their Org Structure for their implementation. The system mandatory levels are Company, Management Unit, Department, Cost Centre, Location and Work Group.

To hide a level:

1. Select the *Hide Indicator*.

Add New Hierarchy Structure

Maintain Hierarchy Structure

Structure Code: ABC ? ABC SOLUTIONS

Description: ABC Solutions

Available Fields	Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode	Reference
Company	ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Code-Description	Reference
Division	DIV	Division			☒	☐	Code-Description	Reference
Management Unit	MGTU	Management Unit			☒	☐	Code-Description	Reference
Department	DEPT	Department			☒	☐	Code-Description	Reference
Cost Centre	COST	Cost Centre			☐	☐	Description	Reference
Location	LOC	Location	1	HEAD OFFICE	☐	☒	Description	Reference
Work Group	WRKGRP	Work Group			☐	☐	Description	Reference
User Field 1					☐	☐	Description	Reference
User Field 2					☐	☐	Description	Reference
User Field 3					☐	☐	Description	Reference
User Field 4					☐	☐	Description	Reference
User Field 5					☐	☐	Description	Reference

Buttons: Save And Close, Save, Cancel, Clear, Activate

2. Set an *Initial Value*.

This is a mandatory step. As the level is mandatory on CoreHR, a default value must be set to ensure that even if the level is hidden on the Post Profile and Contract screens from the user, there is a value set and saved for the record on the system. This will never display to the user but must be stored on the system for all contracts.

3. Click the **Save** button to save the changes.

On the Post Profile Maintenance screen, note that the *Location* field is hidden and does not display.

Post Profile Maintenance

Post Profile

Post Title: PA
Post Number: 502204
Effective Date: 01-JAN-1900
Post Profile Type: P
Managers Order:
Structure Code: ABC

Post Status: ACTIVE
PERMANENT
ABC SOLUTIONS

Auto Authorisation: ☐ Auto Commencement: ☐

Hierarchy Definition

Company: 1000
Division: 1001
Management Unit: HR
Department: HR4
Cost Centre: 1
Work Group: HR4

ABC SOLUTIONS
SHARED SERVICES
HUMAN RESOURCES
PAYROLL
DEFAULT
PAYROLL

Select Detail

- 01 - Post Profile
- 02 - Job Profile
- 03 - Plan Appointments
- 04 - View Appointments
- 05 - Competency Profile
- 06 - Sanction History
- 07 - Status Detail
- 08 - Make Dormant/Reactivate
- 09 - Maintain File

Job Description

Comments

On the Contract screen, note that the *Location* field is hidden and does not display.

View Contract

People Management > Employee Search > Bill Kerry (000100) > View Contract

1 Organizational Structure

Post: 502204 - Payroll Administrator
Sequence: 23

2 Contract Information

Company *: Abc Solutions
Division *: Shared Services
Management Unit *: Human Resources
Department *: HR4 - Payroll
Cost Centre: Default
Location:
Work Group: HR4 - Payroll




corehr
Smarter HR Technology

NEXT

2.2.7. Display Mode

The *Display Mode* setting controls the display of the Org Structure reference data items when creating the linked hierarchy (see [2.5 Linking the Hierarchy](#)).

There are 3 options available:

Option	Display
Description Only the reference data description is displayed.	
Code-Description The level will display using both the reference data code and description in the format: [reference code]-[reference description].	
Description-Code The level will display using both the reference data code and description in the format: [reference description]-[reference code].	

2.2.8. Activate the Organisational Structure

Once the new Organisational Structure has been defined on the system, the next step is to 'Activate' it. This is a mandatory step which must be completed to be able to proceed to linking the hierarchy tree.

To activate the Organisational Structure:

1. Click the **Activate** button

Add New Hierarchy Structure

Maintain Hierarchy Structure

Structure Code: ?

Description:

Available Fields

	Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode	Reference	Icon	
Company	ORGZ	Company	1000	?	ABC SOLUTIONS	☒	☐	Description-Code	Reference	
Division	DIV	Division		?		☒	☐	Description-Code	Reference	
Management Unit	MGTU	Management Unit		?		☒	☐	Description-Code	Reference	
Department	DEPT	Department		?		☒	☐	Description-Code	Reference	
Cost Centre	COST	Cost Centre		?		☐	☐	Description	Reference	
Location	LOC	Location	1	?	HEAD OFFICE	☐	☒	Description	Reference	
Work Group	WRKGRP	Work Group		?		☐	☐	Description	Reference	
User Field 1	USER1	User Field1		?		☐	☐	Description	Reference	
User Field 2				?		☐	☐	Description	Reference	
User Field 3				?		☐	☐	Description	Reference	
User Field 4				?		☐	☐	Description	Reference	
User Field 5				?		☐	☐	Description	Reference	

Buttons: Save And Close, Save, Cancel, Clear, **Activate**

2. A pop-up message will require confirmation to proceed. Click **Yes**.

3. Click the **Save** button or **Save and Close** to save changes.

This activation is not automatically saved so the user must also ensure to click **Save** on screen.

The *Date Applied* will reflect the date that the Organisational Structure was activated i.e.

Maintain Hierarchy Structure

Structure Code: Add New Structure Code Add New Structure

Structure Code	Hierarchy Name	Effective Date	Date Applied	Edit	View	Data
ABC	ABC SOLUTIONS	12-SEP-2017	12-SEP-2017	Edit	View	Data
				Edit	View	Data
				Edit	View	Data
				Edit	View	Data
				Edit	View	Data
				Edit	View	Data

2.3. Edit an Existing Organisational Structure

Note: Extra care should be taken when editing an existing structure that is already in use on CoreHR (i.e. this has been used to define Post Profiles and Contract records) as changes made here will have a downstream impact on existing records. Please consult CoreHR in advance of making any amendments, unless absolutely sure of the impact that this will have.

To edit an existing Organisational Structure:

1. Go to *CorePersonnel > Maintenance > Post Management* and select **Organisational Hierarchy**.

The *Maintain Hierarchy Structure* screen opens.

2. Click the **Edit** button next to the structure to be edited

Structure Code	Hierarchy Name	Effective Date	Date Applied	
ABC	ABC SOLUTIONS	12-SEP-2017	12-SEP-2017	Edit View Data

Note: If a linked hierarchy has been defined for the chosen structure, an alert will appear on screen to warn the user that changes made to the structure may have an impact on this linked hierarchy. Click **Yes** to continue to edit.

The *Add New Hierarchy Structure* screen will pop up

Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode
ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Description-Code Reference
DIV	Division			☒	☐	Description-Code Reference
MGU	Management Unit			☒	☐	Description-Code Reference
DEPT	Department			☒	☐	Description-Code Reference
COST	Cost Centre			☐	☐	Description Reference
LOC	Location	1	HEAD OFFICE	☐	☒	Description Reference
WRKGRP	Work Group			☐	☐	Description Reference
USER1	User Field1			☐	☐	Description Reference
				☐	☐	Description Reference
				☐	☐	Description Reference
				☐	☐	Description Reference
				☐	☐	Description Reference

2.3.1. How to Add a Level

For full guidance on how to add a new level to the structure, follow the steps outlined in [2.2.2 Add Levels to the Structure](#).

If adding a new level, consider the following:

- The label may be updated if required to display an organisation's specific terminology e.g. updating "User Field 1" to something more meaningful.
- It is possible to set:
 - [Initial Value](#)
 - [Hierarchy Indicator](#)
 - [Hide Indicator](#)
 - [Display Mode](#) (relevant only if Hierarchy Indicator is enabled)
- Create any new Reference Data required for the new level (see [2.4 Organisational Structure Reference Data](#)).
- If the *Hierarchy Indicator* has been enabled, ensure that the new level is correctly added to the linked hierarchy (see [2.5 Linking the Hierarchy](#))

Note: Clicking on the links provided above will jump directly to another section in this document where full detailed guidance is provided on each of the options mentioned.

Add New Hierarchy Structure

Maintain Hierarchy Structure

Structure Code: ABC ? ABC SOLUTIONS

Description: ABC Solutions


Available Fields	Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode
Company	ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Code-Description Reference
Division	DIV	Division			☒	☐	Code-Description Reference
Management Unit	MGTU	Management Unit			☒	☐	Code-Description Reference
Department	DEPT	Department			☒	☐	Code-Description Reference
Cost Centre	COST	Cost Centre			☐	☐	Description Reference
Location	LOC	Location			☐	☐	Description Reference
Work Group	WRKGRP	Work Group			☐	☐	Description Reference
User Field 1	USER1	User Field 1			☐	☐	Description Reference
User Field 2					☐	☐	Description Reference
User Field 3					☐	☐	Description Reference
User Field 4					☐	☐	Description Reference
User Field 5					☐	☐	Description Reference

Buttons: Save And Close, Save, Cancel, Clear, Activate

2.3.2. How to Remove a Level

To remove a level from a structure:

1. Click on the  button which is found at the end of each row for every level.
The level will be cleared on screen.
2. Click the **Save** or **Save and Close** button to save changes.



Add New Hierarchy Structure

Maintain Hierarchy Structure

Structure Code: ?


Description:

Available Fields	Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode	Reference
Company	ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Code-Description	Reference 
Division	DIV	Division			☒	☐	Code-Description	Reference 
Management Unit	MGTU	Management Unit			☒	☐	Code-Description	Reference 
Department	DEPT	Department			☒	☐	Code-Description	Reference 
Cost Centre	COST	Cost Centre			☐	☐	Description	Reference 
Location	LOC	Location			☐	☐	Description	Reference 
Work Group	WRKGRP	Work Group			☐	☐	Description	Reference 
User Field 1	USER1	User Field1			☐	☐	Description	Reference 
User Field 2					☐	☐	Description	Reference 
User Field 3					☐	☐	Description	Reference 
User Field 4					☐	☐	Description	Reference 
User Field 5					☐	☐	Description	Reference 

Buttons: Save And Close, Save, Cancel, Clear, Activate

It is not possible to create or save an Organisational Structure if gaps / blank rows exist within the hierarchy e.g. as per screenshot below.

- If removing a level creates a blank row in the middle of the hierarchy, this will not save.
- Ensure that further changes are made to reorder levels, to ensure that no gaps exist (see [2.3.3 How to reorder a level](#))



Add New Hierarchy Structure

Maintain Hierarchy Structure

Structure Code: ?


Description:

Available Fields	Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode	Reference
Company	ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Description-Code	Reference 
Division	DIV	Division			☒	☐	Description-Code	Reference 
Management Unit	MGTU	Management Unit			☒	☐	Description-Code	Reference 
Department	DEPT	Department			☒	☐	Description-Code	Reference 
Cost Centre					☐	☐	Description	Reference 
Location	LOC	Location	1	HEAD OFFICE	☐	☐	Description	Reference 
Work Group	WRKGRP	Work Group			☐	☐	Description	Reference 
User Field 1					☐	☐	Description	Reference 

Please take extra care if removing a level where the *Hierarchy Indicator* is enabled. Removing these levels will have an impact on the linked hierarchy that has been created to include this. For example, if you remove the level “Sub Department” in the below screenshot:

Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode	Reference
ORGZ	Company			☒	☐	Description	Reference
MGTU	Management Unit			☒	☐	Description	Reference
DEPT	Department			☒	☐	Description	Reference
USER1	Sub Department			☒	☐	Description	Reference
WRKGRP	Work Group			☐	☐	Description	Reference
LOC	Location			☐	☐	Description	Reference
COST	Cost Centre			☐	☐	Description	Reference
				☐	☐	Description	Reference
				☐	☐	Description	Reference
				☐	☐	Description	Reference
				☐	☐	Description	Reference

the following pop up will appear:



This will only appear if the level has been included in the linked hierarchy definition. This will not appear if the linked hierarchy has not yet been defined or hasn't included this level as part of the existing definition.

Remember, if removing a level, ensure that the Organisational Structure still includes all mandatory levels (Company, Management Unit, Department, Cost Centre, Location, Work Group) and it will not be possible to save changes to the structure if these are not included.

2.3.3. How to reorder a level

Levels can be reordered on the Organisational Structure by:

- Removing a level to create a gap / blank level.
- Adding a level.

For example, to reorder Work Group and Cost Centre in the below screenshot, the user would need to:

1. Remove Cost Centre.
2. Remove Work Group.
3. Add Cost Centre to the blank row created by removing the Work Group.
4. Add Work Group to the blank row created by removing the Cost Centre.

Add New Hierarchy Structure

Maintain Hierarchy Structure

Structure Code: ABC ? ABC SOLUTIONS

Description: ABC Solutions

Available Fields

Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode
ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Description-Code Reference
DIV	Division			☒	☐	Description-Code Reference
MGTU	Management Unit			☒	☐	Description-Code Reference
DEPT	Department			☒	☐	Description-Code Reference
COST	Cost Centre			☐	☐	Description Reference
LOC	Location	1	HEAD OFFICE	☐	☒	Description Reference
WRKGRP	Work Group			☐	☐	Description Reference
USER1	User Field1			☐	☐	Description Reference
				☐	☐	Description Reference
				☐	☐	Description Reference
				☐	☐	Description Reference
				☐	☐	Description Reference

Buttons: Save And Close, Save, Cancel, Clear, Activate

Please see sections [2.3.2 How to Remove a Level](#) and [2.2.2 Add Levels to the Structure](#) if further guidance is required.

2.4. Organisational Structure Reference Data

Reference Data items must be defined on CoreHR for each of the Organisational Structure levels i.e. the lists of Departments, Cost Centres etc.

Once these have been defined per level, these will be available for selection when:

- Defining the linked hierarchy
- Creating Post Profile records
- Creating new Post Appointment / Contract records

To access the screens required to create new or edit existing reference data items:

1. Go to *CorePersonnel > Maintenance > Post Management* and select **Organisational Hierarchy**.

The *Maintain Hierarchy Structure* screen opens.

2. Click the **Edit** button next to the structure to be edited.

The *Add New Hierarchy Structure* screen opens.

3. Click the **Reference** button that is found at the end of the row for each level.

E.g. to manage Department reference data, click the **Reference** button for the Department row.

Add New Hierarchy Structure

Maintain Hierarchy Structure

Structure Code: ?

Description:

Available Fields	Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode	Reference
Company	ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Code-Description	Reference
Division	DIV	Division			☒	☐	Code-Description	Reference
Management Unit	MGTU	Management Unit			☒	☐	Code-Description	Reference
Department	DEPT	Department			☒	☐	Code-Description	Reference
Cost Centre	COST	Cost Centre			☐	☐	Description	Reference
Location	LOC	Location	1	HEAD OFFICE	☐	☒	Description	Reference
Work Group	WRKGRP	Work Group			☐	☐	Description	Reference
User Field 1					☐	☐	Description	Reference
User Field 2					☐	☐	Description	Reference
User Field 3					☐	☐	Description	Reference
User Field 4					☐	☐	Description	Reference
User Field 5					☐	☐	Description	Reference

Buttons: Save And Close, Save, Cancel, Clear, Activate

In this section, each level will be reviewed in detail as depending on the level required, the Reference Data screens may differ.

2.4.1. Company

Note: The Company reference data is typically managed as part of Payroll Configuration. It is recommended to refer to the Payroll training for further guidance on how to create / update Company Reference Data.

2.4.2. Division

The *Maintain Divisions* screen will open in query mode i.e. this will appear blank:

Division Code	Company Code	Active on Staff Req.	Personnel Inactive
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐

1. Click the  button at the top left of the screen to return all existing Divisions.
2. If no Divisions exist on CoreHR yet, this button must still be clicked in order to update the screen to input mode, so that new records can be entered on screen and saved.

Division Code	Company Code	Active on Staff Req.	Personnel Inactive
1000 SENIOR MANAGEMENT	1000 ABC SOLUTIONS	☒	☐
1001 SHARED SERVICES	1000 ABC SOLUTIONS	☒	☐
1002 SALES & MARKETING	1000 ABC SOLUTIONS	☒	☐
		☐	☐
		☐	☐
		☐	☐
		☐	☐


To add a new Division, update all required fields in the next available blank row. See description of all fields below.

Item	Description	Mandatory
Code	Up to 4 digits only	Yes
Description	Up to 40 alphanumeric characters	Yes
Company Code	Link the Division to an existing Company Code Enter the cursor in the Company Code field and click F9 on the keyboard or  to access the Company list of values.	Yes
Active on Staff Req	Only relevant if using Staff Request in Recruitment.	No
Personnel Inactive	Enabled: The Division is inactive and not available for selection throughout the software on Division lists. Disabled: The Division is active and available for selection throughout the software on Division lists	No

- Repeat for all Divisions required.
- Click the  button to save the reference data items.

2.4.3. Management Unit

The *Maintain Management Units* screen will open in 'input mode' i.e. ready to record new items.



Unit	Description	Analysis Code	Description	Active
FIN	FINANCE			☒
HR	HUMAN RESOURCES			☒
IT	IT			☒
MKT	MARKETING			☒
SALES	SALES			☒
SMGT	SENIOR MANAGEMENT			☒
				☐
				☐
				☐

To add a new Management Unit:


1. Update all required fields in the next available blank row. See description of all fields below.

Item	Description	Mandatory
Code	Up to 6 alphanumeric characters	Yes
Description	Up to 40 alphanumeric characters	Yes
Analysis Code	Optional setting to group reference data items using an Analysis Code. Enter the cursor in the Analysis Code field and click F9 on the keyboard or  to access the Analysis Code list of values.	No
Active	Enabled: The Management Unit is active and available for selection throughout the software on Management Unit lists. Disabled: The Management Unit is inactive and not available for selection throughout the software on Management Unit lists.	Yes

2. Repeat for all Management Units required.
3. Click the  button to save the reference data items.

2.4.4. Department

The *Maintain Department Codes* screen will open in 'input mode' i.e. ready to record new items.



Department Code	Description	Analysis Code	Description	Sensitive Unit	Active
CEO	CEO			☐	☒
FIN1	ACCOUNTS			☐	☒
FIN2	BUDGET			☐	☒
FIN3	TAX			☐	☒
FIN4	FINANCE ADMIN			☐	☒
HR1	RECRUITMENT			☐	☒
HR2	COMPENSATION & BENEFITS			☐	☒
HR3	TRAINING			☐	☒
HR4	PAYROLL			☐	☒
HR5	HR ADMIN			☐	☒
IT1	TECHNICAL SUPPORT			☐	☒
IT2	NETWORKS			☐	☒
IT3	IT SECURITY			☐	☒
M1	LEAD NURTURING			☐	☒

To add a new Department:

1. Update all required fields in the next available blank row. See description of all fields below.

Item	Description	Mandatory
Code	Up to 6 alphanumeric characters	Yes
Description	Up to 40 alphanumeric characters	Yes
Analysis Code	Optional setting to group reference data items using an Analysis Code. Enter the cursor in the Analysis Code field and click F9 on the keyboard or  to access the Analysis Code list of values.	No
Sensitive Unit	If this is enabled, users will require an additional level of access to see employees and posts in this Department. Please Note: This is only available for use in the back-office application for v24. Not available to use in HR Admin.	No
Active	Enabled: The Department is active and available for selection throughout the software on Department lists. Disabled: The Department is inactive and not available for selection throughout the software on Department lists.	Yes

2. Repeat for all Departments required.
3. Click the  button to save the reference data items.

2.4.5. Work Group

Please note: The Work Group reference data is typically managed as part of Workforce Management Configuration. It is recommended to refer to the Workforce Management training for further guidance on how to create / update Work Group reference data.

2.4.6. Cost Centre




Note: The Cost Centre reference data is typically managed as part of Payroll Configuration. It is recommended to refer to the Payroll training for further detailed guidance on how to create / update Cost Centre reference data.

The *Maintain Cost Centre Codes* screen will open in 'input mode' i.e. ready to record new items.

1. Update all required fields in the next available blank row. See description of all fields below.

Item	Description	Mandatory
Code	Up to 13 alphanumeric characters	Yes
Description	Up to 40 alphanumeric characters	Yes
Activity Code	Optional setting to link the reference data items using an Activity Code. Enter the cursor in the Activity Code field and click F9 on the keyboard or  to access the Analysis Code list of values.	No
Active	Enabled: The Cost Centre is active and available for selection throughout the software on Department lists. Disabled: The Cost Centre is inactive and not available for selection throughout the software on Cost Centre lists.	Yes
Link to Hierarchy	Optional feature to allow the user to jump to the Linked Hierarchy definition and add the Cost Centre directly to the Hierarchy. Only relevant if the Cost Centre level has the <i>Hierarchy Indicator</i> flag enabled.	No




Note: This is typically a Payroll field and guidance provided here should be further reviewed in line with the Payroll configuration for an organisation.

2.4.7. Location

The *Location* screen will open in 'input mode' i.e. ready to record new items.

To add a new Location:

1. Update all required fields in the next available blank row. See description of all fields below.

Item	Description	Mandatory
Code	Up to 4 digits only.	Yes
Description	Up to 40 alphanumeric characters.	Yes
Area Code	Optional setting to group Locations items using an Area Code. Enter the cursor in the Area Code field and click F9 on the keyboard or  to access the Area Code list of values.	No
Accum Overseas	Field not applicable.	No
Address	It is possible to define the address associated with each individual location. Up to 5 lines are available per address.	No

2. Repeat for all Locations required.
3. Click the  button to save the reference data items.

Note: There is no 'Active' indicator for Location reference data. All codes listed here will be active and available for selection on Location lists throughout CoreHR.

2.4.8. User Fields 1 – 5

The *User Field 1 – User Field 5* levels are available to enable an organisation to define further levels on their Organisational Structure where more levels are required, outside of the standard 7 levels (i.e. Company, Division, Management Unit, Department, Work Group, Cost Centre, Location).

When a User Field option is added to the Organisational Structure, this will most likely be relabelled. However, when clicking the **Reference** button for one of these items, the screen title will always reflect the User Field # i.e. *Maintain User Field 1 Types*.

The *Maintain User Field # Types* screen will open in 'input mode' i.e. ready to record new items.

To add a new User Field # item:

1. Update all required fields in the next available blank row. See description of all fields below.

Item	Description	Mandatory
User Field #	i.e. Code. Up to 6 alphanumeric characters	Yes
Description	Up to 40 alphanumeric characters	Yes
Analysis Code	Optional setting to group reference data items using an Analysis Code. Enter the cursor in the Analysis Code field and click F9 on the keyboard or  to access the Analysis Code list of values.	No
Active	Enabled: The User Field is active and available for selection throughout the software on User Field lists. Disabled: The User Field is inactive and not available for selection throughout the software on User Field lists.	Yes

2. Repeat for all User Fields required.
3. Click the  button to save the reference data items.

2.5. Linking the Hierarchy


Linking the hierarchy refers to steps taken to create the actual hierarchical representation of the organisation's structure using:

- The levels flagged with the *Hierarchy Indicator*.
- The active reference data created for those levels.

Essentially, this is the process of expanding this:

Available Fields	Org Structure	Label	Initial Value	Description	Hierarchy Indicator	Hide Indicator	Display Mode
Company	ORGZ	Company	1000	ABC SOLUTIONS	☒	☐	Description-Code Reference
Division	DIV	Division			☒	☐	Description-Code Reference
Management Unit	MGTU	Management Unit			☒	☐	Description-Code Reference
Department	DEPT	Department			☒	☐	Description-Code Reference
Cost Centre	COST	Cost Centre			☐	☐	Description Reference
Location	LOC	Location	1	HEAD OFFICE	☐	☒	Description Reference
Work Group	WRKGRP	Work Group			☐	☐	Description Reference
User Field 1	USER1	User Field1			☐	☐	Description Reference
User Field 2					☐	☐	Description Reference
User Field 3					☐	☐	Description Reference
User Field 4					☐	☐	Description Reference
User Field 5					☐	☐	Description Reference

into a tree like structure to include all the reference data items for the levels defined e.g.



Before proceeding, confirm that the following configuration has been completed:

- An Organisational Structure exists
- All required levels for the *data tree* are flagged with the *Hierarchy Indicator*
- Active reference data items exist for all required levels
- The Organisational Structure has been activated.

2.5.1. How to access the Hierarchy Maintenance

To access the *Hierarchy Maintenance* screen where the hierarchy is defined:


1. Go to *CorePersonnel > Maintenance > Post Management* and select **Organisational Hierarchy**.

The *Maintain Hierarchy Structure* screen opens.


2. Click the **Data** button for the required structure



Note: If the structure is not activated, this screen will not open (see [2.2.8 Activate the Organisational Structure](#))



The *Hierarchy Maintenance* screen opens:



Section 1


- This is a view only section of the screen that will display the current *Organisational Hierarchy*.

Section 2

- This is a view only section of the screen that will display the list of levels from the Organisational Structure that have the *Hierarchy Indicator* flag enabled.
- The levels will be displayed in the order that they are configured on other Organisational Structure.

Section 3


- This section provides access to a set of buttons that will allow the user to add or remove the items from each level of the hierarchy.
- The buttons displayed will vary, depending on the item selected in the Hierarchy section (Section 1). For example:
 - In the screenshot above, the top level of the Organisational Structure is selected i.e. the Structure Code = “ABC Solutions”, therefore the only button available is **Add Company**.
 - In the screenshot below, an element at the third level is selected i.e. a Management Unit of “SMGT – Senior Management”, therefore the buttons available are: **Add Management Unit; Add Department; Delete Management Unit**.



At the top of the screen, the *Structure Code* list will only ever include one option i.e. the Structure Code that the Hierarchy is being created for.

The *Search Text* option allows the user to search the configured Hierarchy using a keyword.


- Enter text in the *Search Text* field and click **Find Next**.
- The system will identify Hierarchy Levels that match the search item by highlighting the text in blue.
- Continue to click **Find Next** to identify all matching items in the Hierarchy.



2.5.2. Creating a Hierarchy


If creating a hierarchy from scratch on CoreHR, the user will be prompted with the following message when they access this screen for the first time for a new Structure Code:

“No hierarchy data currently exists. Would you like to create level one of this hierarchy?”



Click **Yes** to proceed.

The screen will automatically update to display the Structure Code and org structure levels.



This will save automatically.


2.5.3. Add a Company / Initial Level

The first level to be added to the Hierarchy will be the top level as defined in the Organisational Structure. This is typically company.


To add the first level to the Hierarchy:

1. Click on the Structure Code in the Hierarchy window e.g. ABC SOLUTIONS below
2. Click on the **Add Company** button on the bottom right of the screen.

The button displays the label for the top level e.g. if the level has been relabelled or if a different element is at the top level.




3. The *Add Company* screen opens:



4. Enable the *Add to Hierarchy* indicator for the required Company / Companies.
 - It is possible to add many records at a time.
 - Use the *Search* box to perform a keyword search on the list of Companies.

5. Click the **Add** button.

The pop-up window closes and the Company (or other level) will be displayed in the Hierarchy section of the screen.




The text displayed for the Level on this screen is dependent on the *Display Mode* set for that level when defining the Organisational Structure (see [2.2.7 Display Mode](#))

6. Select that first level in the Hierarchy section and note that there are now three new buttons available at the bottom right of the screen – in the screenshot above, based on that Organisational Structure, these are:
 - Add Company
 - Add Division
 - Delete Company

2.5.4. Add Levels to the Hierarchy

All levels are added to the Hierarchy in the same way.

1. Select the level in the Hierarchy that you wish to add another element beneath e.g.
in the screenshot below, the *Division* (i.e. Level 2) of “1001 – Shared Services” is selected.



The buttons at the bottom right of the screen update accordingly e.g.

- **Add Division** (i.e. add another element for the current level)
- **Add Management Unit** i.e. (or add an element for the next level down)
- **Delete Division** (i.e. or delete the current element selected at this level.)

The buttons available will differ depending on the level of the Hierarchy element select e.g. if a *Management Unit* was selected in the above screenshot these would display:

- **Add Management Unit**
- **Add Department**
- **Delete Add Management Unit**

2. Click on the required **Add** button and the corresponding *Add* screen will display.
 - In this example, we will add a new Management Unit beneath the “Shared Services” Division.
3. On the *Add* screen, search for the required item and enable the *Add to Hierarchy* checkbox

- The levels displayed at the top of the screen identify where in the Hierarchy these items will be added beneath i.e. these will be added under “Shared Services” Division.
- It is possible to select many items on this screen to add at once.
- If an item has already been added to this branch of the Hierarchy, it will not be listed on this screen e.g. if Finance has already been configured, it would not be listed here

Add Management Unit

Hierarchy Maintenance

Level 1: Company ABC SOLUTIONS - 1000
 Level 2: Division SHARED SERVICES - 1001
 Level 3: Management Unit -

Include Linked Items ☐

Search

Management Unit	Description	Add To Hierarchy
FIN	FINANCE	☒
HR	HUMAN RESOURCES	☒
IT	IT	☒
MKT	MARKETING	☐
SALES	SALES	☐
		☐
		☐
		☐
		☐
		☐

4. Click the **Add** button to add all selected items

Hierarchy Maintenance

Structure Code: ABC SOLUTIONS
 Search Text:

Hierarchy

- ABC SOLUTIONS
 - ABC SOLUTIONS - 1000
 - SALES & MARKETING - 1002
 - SENIOR MANAGEMENT - 1000
 - SHARED SERVICES - 1001
 - FINANCE - FIN
 - HUMAN RESOURCES - HR
 - IT - IT

Hierarchy Configuration

Structure Code: ABC SOLUTIONS


Level 1: Company
 Level 2: Division
 Level 3: Management Unit
 Level 4: Department

The new items will display on the Hierarchy.

5. Select one of the new items on the Hierarchy, to update the buttons on screen so that the items can be added to the remaining lower levels in that branch of the Hierarchy.

Once the lowest level has been reached i.e. the last level on the Organisational Structure where the *Linked Hierarchy* indicator is enabled, only 2 buttons will be available e.g.

- Department is the lowest level in the example in the screenshot below.
- The Department of “Technical Support” is selected.
- There is no option to add a level beneath this department.
- There is an option to:
 - **Add Department** i.e. add another item at the current level
 - **Delete Department** i.e. delete the selected item from the Hierarchy.



5. Repeat the steps above to define all the levels for all branches of the Hierarchy i.e. click on an element in the Hierarchy and use the **Add** buttons to add the items required beneath that level.




Note: All **changes are saved immediately** on this screen i.e. once an item is added or removed, there is no further requirement to save this. Caution is advised if amending an existing Hierarchy that is currently in use, as this can have a direct impact on exiting Post Profile and Post Appointment / Contract records.

2.5.5. Remove a Level


To remove an element from the Hierarchy:

1. Select the item in the Hierarchy e.g. "Shared Services".
2. Click the corresponding **Delete** button at the bottom right of the screen
 - E.g. **Delete Division**
 - The buttons update to display the level of the element select.



3. If there are further elements defined beneath that selected element, the all further sub-elements will be deleted.

A pop-up alert will require you to confirm that you are happy to delete this.



Note: All **changes are saved immediately** on this screen i.e. once an item is added or removed, there is no further requirement to save this. Caution is advised if amending an existing Hierarchy that is currently in use, as this can have a direct impact on exiting Post Profile and Post Appointment / Contract records.

2.5.6. Shared Hierarchy Elements

It is possible to add the same element to multiple branches of the hierarchy. This may be necessary, depending on an organisation's specific requirements.

When adding an element to the Hierarchy, ensure the **Include Linked Items** flag is enabled.

This will ensure that the list of elements displayed on screen will reflect the list of all:

- Elements that have not yet been included in any branch of the hierarchy
- Elements that have been included in other branches of the hierarchy

Add Management Unit

Hierarchy Maintenance

Level 1: Company 1000 - ABC SOLUTIONS
Level 2: Division 1001 - SHARED SERVICES
Level 3: Management Unit -

Include Linked Items ☒

Search Search

Management Unit	Description
MKT	MARKETING
SALES	SALES
SMGT	SENIOR MANAGEMENT

Add To Hierarchy ☐

Add Cancel


2.6. Other Configuration Options

2.6.1. Default to Collapse / Expand Hierarchy Display

It is possible to configure the display of the linked hierarchy to be either fully collapsed or fully expanded, when the screen is accessed.


This is controlled via the following parameter:

1. Go to *Reference > Reference Q -Z > System Parameters – Advanced*
2. Click the **Client Parameters** button
3. On the *Client Parameters* screen search for the parameter:
“Collapse Hierarchy Tree in PER755”




Enabled:

The hierarchy will be fully collapsed to the highest level i.e. *Structure Code*.



Disabled

All levels of the hierarchy will be fully expanded




2.7. Menu Options

2.7.1. Organisational Hierarchy

To access the Organisational Hierarchy screens, the following Menu Options are required:

Installed System	Menu Option
CorePersonnel	Post Management Menu-Organisational Hierarchy



This menu option will provide access to the *Maintain Hierarchy Structure* screen and all screens within that.

This will not provide access to the reference data screens for the hierarchy levels. Further menu options are required for this and listed in this document.

2.7.2. Company Reference Data

This menu option is required to access the screen used to manage *Company* reference data (see [2.4.1 Company](#)).

Installed System	Menu Option
CorePersonnel	Reference Menu K-P-Maintain Organisations

2.7.3. Management Unit

This menu option is required to access the screen used to manage *Management Unit* reference data (see [2.4.3 Management Unit](#)).

Installed System	Menu Option
CorePersonnel	Reference Menu K-P-Management Units

2.7.4. Department

This menu option is required to access the screen used to manage *Department* reference data (see [2.4.4 Department](#)).

Installed System	Menu Option
CorePersonnel	Reference Menu D-J-Departments

2.7.5. Division

This menu option is required to access the screen used to manage *Division* reference data (see [2.4.2 Division](#)).

Installed System	Menu Option
CorePay	Corporate Menu - Maintain Divisions

2.7.6. Location

This menu option is required to access the screen used to manage *Location* reference data (see [2.4.7 Location](#)).

Installed System	Menu Option
CorePersonnel	Reference Menu K-P-Location_Codes

2.8. Auto-Fill Hierarchy

This feature allows users to create and manage an organisation's hierarchy structures using the modern UI within CorePortal. Selecting a hierarchy level mean that on the following wizards, the hierarchy is auto-filled from that level upwards through each higher level defined.

- a. Staff Request management.


- b. Post Profile management.
- c. Contract management.

Access to this feature is controlled by the following menu option:


System	Menu Option	Description
People Management	Structure Setup	This allows access to the Structure Setup screen on the Data Centre widget in CorePortal.

2.8.1. Configuring Auto-Fill Hierarchy


2. Quick Jump to the Data Centre on the People Management dashboard.




3. Click on the **Open** button alongside the *People Management* label.



4. Search for *Structure Setup* and click on the corresponding button.



5. The *Structure Setup* screen opens.




Note: All existing Organisational Structures are listed on screen.


The table below shows what appears on this screen:

Item	Description
Search Structure	This allows you to search on a structures name.
Name	This is the name of the Hierarchy Structure.
Date Effective	This is the date at which the Hierarchy structure is effective from.
Date Activated	This is the date at which the hierarchy structure was made active.
Date Deactivated	This is the date at which the hierarchy was made inactive or dormant.
New Structure	This allows you to create a new structure on the system.
View	This allows you to view the structure in read-only mode.
Edit	This allows you to make changes to the hierarchy structure.
Deactivate	This allows you to deactivate the structure from todays date.

6. Click on the **View** button



- On the Structure screen, click on the **Autofill Level Type** option.
- A drop-down menu appears with the existing Level Types (Hierarchy Fields) that have been flagged as linked to the hierarchy.



- Decide on the level from which the hierarchy is to be auto-filled from.
- Click the **Save** button.

Structure Setup

ABC Solutions

People Management > View All > Structure Setup > ABC Solutions

Structure saved successfully

Structure

Date Effective: 11-Mar-2016

Date Activated: 11-Mar-2016

Autofill Level Type: Company

Structure Detail

Position	Level Type	Label	Level Default	Display Mode	Hierarchy	Hidden	
1	Company	Company	Abc Solutions	Description-Code	☒	☐	DELETE
2	Division	Division		Description-Code	☒	☐	DELETE
3	Management Unit	Management Unit		Description-Code	☒	☐	DELETE

SAVE

2.8.2. Auto-Filled Staff Request Wizard

On the Staff Request creation wizard, select a structure and follow this up with selecting the reference data from the auto-fill configuration. For example, in the image below, the auto-fill configuration is setup at Department level. Therefore, when a chosen Department is selected, the levels above it are automatically completed.

1. Company: ABC Solutions
2. Division: Sales & Marketing
3. Management Unit: Marketing
4. Department: Digital Marketing

← Staff Requests

New Staff Request

Manager Dashboard > Staff Requests > New Staff Request

1 Position

2 Contract

3 Job Details

4 Vacancy Details

Structure

ABC Solutions

Autofill from Department

Digital Marketing

Hierarchy

Company *

ABC Solutions

Division *

Sales & Marketing

Management Unit *

Marketing

Department *

M3 - Digital Marketing

NEXT

2.8.3. Auto-Filled Post Profile Wizard

On the Post Profile creation wizard, select a structure and follow this up with selecting the reference data from the auto-fill configuration. For example, in the image below, the auto-fill configuration is setup at Department level. Therefore, when a chosen Department is selected, the levels above it are automatically completed.

1. Company: ABC Solutions
2. Division: Sales & Marketing
3. Management Unit: Sales
4. Department: Menswear

Post Profile Maintenance

Post Profile Wizard

People Management > People Management > Post Profile Maintenance > Post Profile Wizard

1 Organisational Structure

2 Post Details

Autofill from Department

Menswear

Structure *

Company *

Division

Management Unit

Department

1

2

3

4

ABC SOLUTIONS

ABC SOLUTIONS

SALES & MARKETING

SALES

S1 - MENSWEAR

NEXT

2.8.4. Auto-Filled Contract Wizard

Choose Contract

Replace Appointment

People Management > Employee Search > Adara Goodman (000162) > Choose Contract > Replace Appointment

POST SEARCH

1 Organizational Structure

2 Contract Information

3 Salary Information

Post

502203 - Payroll Manager

Autofill from Department

Payroll

Company *

Division *

Management Unit *

Department *

Cost Centre

ABC SOLUTIONS

SHARED SERVICES

HUMAN RESOURCES

HR4 - PAYROLL

COST CENTRE *

NEXT

2.8.5. Auto-Filled New Contract Wizard

← Duplicate Employee Check

DC

New Starter

People Management > Search for Post > Duplicate Employee Check > New Starter

POST SEARCH

1 Person Information

2 Organizational Structure

3 Contract Information

4 Salary Information

Post

502219 - Budget Analyst

Autofill from Department

Company *

Abc Solutions

Division *

Shared Services

Management Unit *

Finance

Department *

FIN2 - Budget

Cost Centre

Cost Centre *

corehr

PREVIOUS

NEXT