## Grupo05 Eberton, Elisangela, Gabriel Semana 06

Conexão com servidor sem erros

```
// > --/Documents/UFU/bd2/JDBCTutorial

) ./comp JDBCUtilities properties/postgres-properties-error.xml

Reading properties file /home/bits/Documents/UFU/bd2/JDBCTutorial/properties/postgres-properties-error.xml

Set the following properties:

dbms: postgresql

driver: postgresql

ddName: ib2

userName: postgres

serverName: localhost
portNumber: 5433

Connected to database

Releasing all open resources ...
```

Alterando senha de conexão

```
./comp JDBCUtilities properties/postgres-properties-error.xml
Reading properties file /home/bits/Documents/UFU/bd2/JDBCTutorial/properties/postgres-properties-error.xml
Set the following properties:
dbms: postgresql
driver: postgresql
dbName: ib2
userName: postgres
serverName: localhost
portNumber: 5433
org.postgresql.util.PSQLException: FATAL: password authentication failed for user "postgres"
         at org.postgresql.core.v3.ConnectionFactoryImpl.doAuthentication(ConnectionFactoryImpl.java:463)
         at org.postgresql.core.v3.ConnectionFactoryImpl.openConnectionImpl(ConnectionFactoryImpl.java:203)
        at org.postgresql.core.ConnectionFactory.openConnection(ConnectionFactory.java:49) at org.postgresql.jdbc.PgConnection.<init>(PgConnection.java:195) at org.postgresql.Driver.makeConnection(Driver.java:454)
        at org.postgresql.Driver.connect(Driver.java:256) at java.sql.DriverManager.getConnection(DriverManager.java:664)
         at java.sql.DriverManager.getConnection(DriverManager.java:208)
         at com.oracle.tutorial.jdbc.JDBCUtilities.getConnection(JDBCUtilities.java:169)
        at com.oracle.tutorial.jdbc.JDBCUtilities.main(JDBCUtilities.java:214)
SQLState: 28P01
Error Code: 0
Message: FATAL: password authentication failed for user "postgres"
Releasing all open resources ...
```

Retirando traceback

```
// > ~/Documents/UFU/bd2/JDBCTutorial
// ./comp JDBCUtilities properties/postgres-properties-error.xml
Reading properties file /home/bits/Documents/UFU/bd2/JDBCTutorial/properties/postgres-properties-error.xml
Set the following properties:
dbms: postgresql
driver: postgresql
driver: postgresql
dbName: ib2
userName: postgres
serverName: localhost
portNumber: 5433
SQLState: 28P01
Error Code: 0
Message: FATAL: password authentication failed for user "postgres"
Releasing all open resources ...
```

Adiconando erro customizado para senha

```
// Comp JDBCUtilities properties/postgres-properties-error.xml
Post the following properties:

// Comp JDBCUtilities file /home/bits/Documents/UFU/bd2/JDBCTutorial/properties/postgres-properties-error.xml

// Set the following properties:

// Set the following properties

// Set the foll
```

• Erro customizado para número da porta

```
p = ~/Documents/UFU/bd2/JDBCTutorial
) ./comp JDBCUtilities properties/postgres-properties-error.xml
Reading properties file /home/bits/Documents/UFU/bd2/JDBCTutorial/properties/postgres-properties-error.xml
Set the following properties:
dbms: postgresql
driver: postgresql
driver: postgresql
dobName: ib2
userName: postgres
serverName: localhost
portNumber: 5432

Você está batendo na porta errada!!!
Tenta na casa ao lado ;) '5433'

SQLState: 08001
Error Code: 0
Message: Connection to localhost:5432 refused. Check that the hostname and port are correct and that the postmaster is accepting TCP/IP connections. Cause: java.net.ConnectException: Connection refused (Connection refused)
Releasing all open resources ...
```