Reg.No.: 2116220701040

## Practical 8

## AIM:-

b) Configuration of Wireless LAN using CISCO Packet Tracer.

## Procedure:

- 1. Click Network Devices from below, click Wireless Network devices, Select wireless router in centre.
- **2.** Click End devices and add 3Pc's top of the router.
- 3. Click router  $\rightarrow$  GUI tab check given ip address is 192.168.0.1  $\rightarrow$  click, click disabled and save settings.
- **4.** Come up click wireless → wireless settings, Change network name (SSID) to MyHomeNetwork, Save settings.
- **5.** Come up again, click wireless setting, security mode change to WEP give key1 as 0123456789, Save and close the tab.
- **6.** Click PC1, desktop, Ip configuration

IP address  $\rightarrow$  192.168.0.5

Subnet Mask  $\rightarrow$  255.255.255.0

Default gateway  $\rightarrow$  192.168.0.1, Close the tab

7. Go to PC2, desktop, Ip configuration

IP address  $\rightarrow$  192.168.0.6

Subnet Mask  $\rightarrow$  255.255.255.0

Default gateway  $\rightarrow$  192.168.0.1, Close the tab

**8.** Go to PC3, desktop, Ip configuration

IP address  $\rightarrow$  192.168.0.7

Subnet Mask  $\rightarrow$  255.255.255.0

Default gateway  $\rightarrow$  192.168.0.1, Close the tab

- 9. Again click PC1  $\rightarrow$  Pc wireless  $\rightarrow$  Error will occur  $\rightarrow$  Close the tab.
- 10.On top go to physical tab → turn off the pc → go down drag the module which is inside and drop it in left side and take WMP300N in the module place and turn on the PC.
- 11.Go to the desktop tab on the top → PC wireless → Connect → WEP key →0123456789, Connect now when you click link information it will show you have successfully connected. Close the tab.
- 12. Repeat the process for PC2 and PC3.

**13.**To check the connectivity whether all is connected click any PC, Command Prompt any IP address given during this process → ping 192.168.0.6 and give enter.

## **OUTPUT**:



