Rowan University
Computer Network
LAB-SESSION

Instructions:

The student must recreate the scenario through Packet tracer software according to the study case denominated Lab-One.

Study Case: Lab-One

Create a scenario that contains the following components:
One hub --------------> Generic ---> Hub-PT ---> Hub0
Four Pc's ------------> Generic ---> PC-PT ---> PC01
---> PC02
---> PC03
---> PC04

Step#1:
On the bottom from the Cisco Packet Tracer application, click on the icon hubs and then on Generic Hub to drag-drop on the main section. See the Fig N° 1. The same action from icon End Devices/Generic four times. See the Fig N° 2




Fig N° 1




Fig N° 2




Fig N° 3

On the main section, you can see the hub with four Pcs. See Fig N° 3. Then double click on the name PC1 and switch with the name PC01. Then the same way for PC2, PC3, and PC4 with the names PC02, PC03, and PC04. See Fig N° 4.




Fig N° 4

Step#2:

Double-click on the PC01 (See Fig N° 5) and click on the Desktop tab/IP configuration (See Fig N° 6). Then enter the IP Address: 192.168.1.1 and the Subnet Mask: 255.255.255.0 (See Fig N° 7)




Fig N° 5



Fig N° 6




Fig N° 7

Step#3:


Repeat Step#2 for PC02, PC03, and PC04 with the following information.

PC02
IP Address:----> 192.168.1.2
Subnet Mask:---> 255.255.255.0


PC03
IP Address:----> 192.168.1.3
Subnet Mask:---> 255.255.255.0

PC04
IP Address:----> 192.168.1.4
Subnet Mask:---> 255.255.255.0


PC01




PC02



PC03



PC04



Step#4:

On the bottom from the Cisco Packet Tracer application, click on the icon Connections and then on Automatically choose Connection Type (see Fig N° 8). Then click on the PC01 and click on Hub-PT. (see Fig N° 9).




Fig N° 8




Fig N° 9

Repeat the actions, to connect PC02, PC03, and PC04 WITH Hub-PT. See Fig N° 10





Fig N° 10

Step#5:

Communicate between PC01 to PC04. On the right from Cisco Packet Tracer application, click on the icon Add simpl PDU (P). (See Fig N° 11).

Fig N° 11



Then click first at PC01 and second at PC04. (See Fig N° 12). After on the corner-botom click on the icon Simulation (See Fig N° 13).




Fig N° 12




Fig N° 13

Step#6:

Click on the button <<Capture/Forward>> (See Fig N° 14), Verify step by step the complete process to communicate between PC01 to PC02.




Fig N° 14

***