

Aexeo - Active PnL - COMAPI

- [I. UiPath Library Owner](#)
- [II. Objective](#)
- [III. Library Details](#)
 - [Overview](#)
 - [Pre-requisites](#)
 - [Arguments](#)
 - [Orchestrator Assets](#)
 - [Directories](#)
 - [How to Use](#)
- [IV. Testing](#)
- [V. References](#)
- [VI. Enhancements](#)

I. UiPath Library Owner

Resource	Role	Jira item
@Estrella, Daniel (Citco)	Developer	☒ IA-7727: UI Path - Shared Component - Active PnL COMAPI PI Done

II. Objective

This page is created to discuss the flow of calling Aexeo Active PnL - COMAPI Library.

III. Library Details

Item	Description
Project Name	IA.Aexeo.ActivePnL.COMAPI
Version	1.0.3

Overview

- Receives Report Criteria for P&L
- Creates Payload in JSON Format
- Invoke Aexeo Active PnL COMAPI JavaScript
- Wait for Report to Generate and move to save location

Pre-requisites

- ActivePnlComApi should be installed on the machine will be used to run

Installer: [ActivePnlComApi-2021.08.421.00.Installer.exe](#)

Arguments

Name	Direction	Argument Type	Required Field (Y/N)	Description	Sample
in_dt_ReportCriteria	In	DataTable	Y	Report Criteria for P&L in DataTable	
in_ClientName	In	String	Y	Name of Client	CS_HEDGING_GRIFFO4
in_FileName	In	String	Y	File Name to use (Without Extension)	CS_HEDGING_GRIFFO4_ActivePnl_YYYYMMDD
in_SaveLocation	In	String	Y	Directory to Save the report	\\uiopath-share.int.coreprod01.citcosvc.com\UiPathShare\nonprod\UiPathProjects\ia-uipath-library-aexeo-activepnl-comapi
in_ComApiTimeout	In	Int32	N	Optional Timeout in minutes to use in threshold (Default will be 60)	60

in_ComApiGridviewType	In	String	N	Optional View to use when using Active Grid View criteria (Default will be global)	“global” or “client”
in_ComApiSaveCsvMethod	In	String	N	Optional Method of CSV to save (Default is “SaveAsRawCSV”)	SaveAsRawCSV or SaveAsCSV
out_ComApiMessage	Out	String	N/A	Message from COMAPI run	
out_bool_ComApiSuccess	Out	Boolean	N/A	Bool flag returned from COMAPI run	True or False

Orchestrator Assets

Asset Name	Asset Type	Description
Aexeo.ActivePnl.ComApi.UiPathShare	Text	UiPath Share Drive
Aexeo.ActivePnl.ComApi.Timeout	Integer	Default API Timeout
Aexeo.ActivePnl.ComApi.Script	Text	JavaScript Used for COMAPI
Aexeo.ActivePnl.ComApi.Credentials	Credentials	Encoded credentials for Aexeo Active Pnl ComApi generation


Directories

Directory	Description	Notes
-----------	-------------	-------

\\uipath-share.int.coreprod01.citcosvc.com\UiPathShare\nonprod\UiPathProjects\ia-uipath-library-aexeo-activepnl-comapi\LOGS	Contains logs for every time the library was called/used	- CS_HEDGING_GRIFFO_SEA1WS80044_ActivePnlComApi_COMPLETED_20240716_1220.log - CS_HEDGING_GRIFFO_SEA1WS80044_ActivePnlComApi_FAILED_20240716_0738.log
\\uipath-share.int.coreprod01.citcosvc.com\UiPathShare\nonprod\UiPathProjects\ia-uipath-library-aexeo-activepnl-comapi\REQUESTS	Contains requests files generated by the library.	- CS_HEDGING_GRIFFO_ActivePnl_202407161217.end - CS_HEDGING_GRIFFO_ActivePnl_202407161217.json - CS_HEDGING_GRIFFO_ActivePnl_202407160736_ErrorLog.err
\\uipath-share.int.coreprod01.citcosvc.com\UiPathShare\nonprod\UiPathProjects\ia-uipath-library-aexeo-activepnl-comapi\SCRIPTS	Contains Java Scripts used by the library	ActivePnlComApi.js


How to Use

1. Install Library to the project in UiPath Studio. (Navigate to Manage Packages)




2. Search for the Library - IA_Aexeo.ActivePnl.ComApi

Note: Install the most updated version



3. Library will now be available in the activity panel and ready to use:



IV. Testing

\\uipath-file-share.int.coreprod01.citcosvc.com\UiPathShare\nonprod\UiPathProjects\ia-uipath-library-aexeo-activepnl-comapi\OUTPUTS

V. References

☒ [IA-7727: UI Path - Shared Component - Active PnL COMAPI](#) Done

VI. Enhancements