




NAME : SRISTI BHOWMICK , COLLEGE ROLL : BTECH/CSE/23/095 , EXAM ROLL : 11600223120

ASSIGNMENT 7: Hosting a website on EC2.

STEP1: After login -> click on Ec2 -> Click instances(left) -> Launch instance -> Give instance name and select ubuntu -> Create a Key pair -> Check all boxes and Instance created.



aws [Search] [Alt+S] Asia Pacific (Mumbai) Sriшти Bhowmick (0217-5467-6955) Sriшти Bhowmick

EC2 > Instances > Launch an instance

Instance type

Info | Get advice

Instance type

t3.micro
Family: t3 2 vCPU 1 GiB Memory Current generation: true Free tier eligible

On-Demand Linux base pricing: 0.0112 USD per Hour On-Demand SUSE base pricing: 0.0112 USD per Hour
On-Demand Windows base pricing: 0.0204 USD per Hour On-Demand RHEL base pricing: 0.04 USD per Hour
On-Demand Ubuntu Pro base pricing: 0.0147 USD per Hour

Additional costs apply for AMIs with pre-installed software

All generations Compare instance types

Key pair (login)

Info

You can use a key pair to securely connect to your instance. Ensure that you have access to the selected key pair before you launch the instance.

Key pair name - required

Select Create new key pair

Network settings

Info

Network vpc-0a874208a064ece04

Subnet No preference (Default subnet in any availability zone)

Auto-assign public IP Enable

Firewall (security groups) A security group is a set of firewall rules that control the traffic for your instance. Add rules to allow specific traffic to reach your instance.

Edit

Summary

Number of instances 1

Software image (AMI)
Canonical, Ubuntu, 24.04, amd64...read more
ami-019715e0d74f695be

Virtual server type (instance type)
t3.micro

Firewall (security group)
New security group

Storage (volumes)
1 volume(s) - 8 GiB

Cancel Launch instance Preview code

Create key pair

Key pair name

Key pairs allow you to connect to your instance securely.

key2

The name can include up to 255 ASCII characters. It can't include leading or trailing spaces.

Key pair type

☒ RSA
RSA encrypted private and public key pair

☐ ED25519
ED25519 encrypted private and public key pair

Private key file format

☒ .pem
For use with OpenSSH

☐ .ppk
For use with PuTTY

⚠ When prompted, store the private key in a secure and accessible location on your computer. You will need it later to connect to your instance. [Learn more](#)

Cancel Create key pair

key2.pem
1,678 B • Done

aws

Search

[Alt+S]

Asia Pacific (Mumbai)

Sristi Bhowmick (0217-5467-6955)

Sristi Bhowmick

EC2 > Instances > Launch an instance

▼ Key pair (login) Info

You can use a key pair to securely connect to your instance. Ensure that you have access to the selected key pair before you launch the instance.

Key pair name - required

key2

Create new key pair

▼ Network settings Info

Edit

Network Info

vpc-0a874208a064ece04

Subnet Info

No preference (Default subnet in any availability zone)

Auto-assign public IP Info

Enable

Firewall (security groups) Info

A security group is a set of firewall rules that control the traffic for your instance. Add rules to allow specific traffic to reach your instance.

Create security group

Select existing security group

We'll create a new security group called 'launch-wizard-2' with the following rules:

☒ Allow SSH traffic from

Helps you connect to your instance

Anywhere

0.0.0.0/0

☒ Allow HTTPS traffic from the internet

To set up an endpoint, for example when creating a web server

☒ Allow HTTP traffic from the internet

To set up an endpoint, for example when creating a web server

▼ Summary

Number of instances Info

1

Software Image (AMI)

Canonical, Ubuntu, 24.04, amd64...read more

ami-019715e0d74f695be

Virtual server type (instance type)

t3.micro

Firewall (security group)

New security group

Storage (volumes)

1 volume(s) - 8 GiB

Cancel

Launch instance

Preview code

aws

Search

[Alt+S]

Asia Pacific (Mumbai)

Sristi Bhowmick (0217-5467-6955)

Sristi Bhowmick

EC2 > Instances

EC2

Dashboard

AWS Global View

Events

▼ Instances

Instances

Instance Types

Launch Templates

Spot Requests

Savings Plans

Reserved Instances

Instances (1) Info

Last updated 1 minute ago

Connect

Instance state

Actions

Launch instances

Find Instance by attribute or tag (case-sensitive)

All states

< 1 >

	Name	Instance ID	Instance state	Instance type	Status check	Alarm status	Availability Zone	Public IPv4 DNS
☐	sristi10	i-04ddb02a26ba26775	Running	t3.micro	Initializing	View alarms +	ap-south-1b	ec2-13-233-152-102.ia

aws

Search

[Alt+S]

Asia Pacific (Mumbai)

Sristi Bhowmick (0217-5467-6955)

Sristi Bhowmick

EC2 > Instances > i-04ddb02a26ba26775

EC2

Dashboard

AWS Global View

Events

▼ Instances

Instances

Instance Types

Launch Templates

Spot Requests

Savings Plans

Reserved Instances

Dedicated Hosts

Capacity Reservations

Capacity Manager New

▼ Images

AMIs

AMI Catalog

▼ Elastic Block Store

Volumes

Snapshots

Instance summary for i-04ddb02a26ba26775 (sristi10) Info

Updated less than a minute ago

Connect

Instance state

Actions

Instance ID

i-04ddb02a26ba26775

IPv6 address

-

Hostname type

IP name: ip-172-31-4-167.ap-south-1.compute.internal

Answer private resource DNS name

IPv4 (A)

Auto-assigned IP address

13.233.152.102 [Public IP]

IAM role

-

IMDSv2

Required

Operator

-

Public IPv4 address

13.233.152.102 | open address

Instance state

Running

Private IP DNS name (IPv4 only)

ip-172-31-4-167.ap-south-1.compute.internal

Instance type

t3.micro

VPC ID

vpc-0a874208a064ece04

Subnet ID

subnet-0f94e0905aad52965

Instance ARN

arn:aws:ec2:ap-south-1:021754676955:instance/i-04ddb02a26ba26775

Private IPv4 addresses

172.31.4.167

Public DNS

ec2-13-233-152-102.ap-south-1.compute.amazonaws.com | open address

Elastic IP addresses

-

AWS Compute Optimizer finding

Opt-in to AWS Compute Optimizer for recommendations. | Learn more




Auto Scaling Group name

-

Managed

false

STEP 2: Copy public IPV4 address -> open Bitwise ssh client -> paste address in host , username = ubuntu, initial method = publickey -> go to client key manager -> import key2.pem -> login (in left there a terminal console appeared)




STEP 3: OPEN NEW TERMINAL CONSOLE -> EXECUTE COMMAND -> 1. sudo apt-get update -> 2. Sudo apt-get upgrade -> sudo apt-get install nginx




```
ubuntu@13.233.152.102:22 - Bitvise xterm - ubuntu@ip-172-31-4-167: ~  
  
The programs included with the Ubuntu system are free software;  
the exact distribution terms for each program are described in the  
individual files in /usr/share/doc/*/copyright.  
  
Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by  
applicable law.  
  
To run a command as administrator (user "root"), use "sudo <command>".  
See "man sudo_root" for details.  
  
ubuntu@ip-172-31-4-167:~$ sudo apt-get update  
Hit:1 http://ap-south-1.ec2.archive.ubuntu.com/ubuntu noble InRelease  
Get:2 http://ap-south-1.ec2.archive.ubuntu.com/ubuntu noble-updates InRelease [126 kB]
```


```
ubuntu@13.233.152.102:22 - Bitvise xterm - ubuntu@ip-172-31-4-167: ~  
Reading package lists... Done  
ubuntu@ip-172-31-4-167:~$ sudo apt-get upgrade  
Reading package lists... Done  
Building dependency tree... Done  
Reading state information... Done  
Calculating upgrade... Done  
The following upgrades have been deferred due to phasing:
```

```
ubuntu@ip-172-31-4-167:~$ sudo apt-get install nginx  
Reading package lists... Done  
Building dependency tree... Done
```

STEP 4: AGAIN IN BITVISE SSH OPEN NEW SFTP WINDOW -> BACK TO ROOT FOLDER -> THEN VAR -> WWW-> HTML-> INITIALLY A DEFAULT NGINX HTML FILE -> GO TO TERMINAL AGAIN -> COMMANDS -> cd .. -> cd .. -> cd var -> cd www-> sudo chmod 777 html -> upload a local file to remote file -> refresh the site -> it will be the new file







STEP 5: Back to aws console -> click on instances -> check the box -> click on instance state -> terminate instance .

